

POSHPET

Phase 1 Technical Documentation

Document 1 of 5: Foundation

[Project Overview](#) | [Technology Stack](#) | [Design System](#) | [Roadmap](#)

Version 3.0 | February 2026

TABLE OF CONTENTS

PART 1: PROJECT OVERVIEW

1.1 What is PoshPet Phase 1?

PoshPet is a luxury daily pet care planner that transforms routine pet care from a mechanical chore into a beautiful, mindful ritual. Positioned as *Headspace meets Duolingo for pet parents*, PoshPet combines elegant design, intelligent gamification, and genuine emotional connection to help users provide consistent, devoted care to their pets.

The core insight behind PoshPet is that pet care is not just about task completion. Every walk, every meal, every grooming session is an act of love. PoshPet captures, celebrates, and preserves these moments in ways no other app attempts.

Product Positioning

Premium Tier: \$14.99/month or \$149.99/year (PoshPet Society membership)

Target Audience: Affluent pet parents (household income \$75K+) who view pets as family members. Women aged 28-45, urban/suburban, college-educated, already spending on premium pet services.

Market Position: Competing with Calm, Headspace, and Notion for subscription budget. NOT competing with free clinical pet trackers.

Aesthetic Direction: Luxury spa meets productivity app. Warm, organic, nature-inspired. Premium without pretension.

Emotional Promise: *Turn daily pet care into a love story* — captured forever, celebrated intentionally, remembered always.

1.2 The Problem We Solve

Pet parents currently rely on four inadequate methods: sticky notes (lost, no history), phone reminders (no context, easy to ignore), pure memory (forgotten medications, anxiety), and clinical pet tracking apps (70% abandonment in 2 weeks due to overwhelming medical interfaces). Beyond these practical failures, existing solutions fail to address the emotional needs of pet parents: guilt from forgetting tasks, no reward for daily care, years of devotion that leave no lasting record, and no tools for celebrating milestones intentionally.

1.3 Six Core Innovations

Innovation 1: Beautiful Visual Progress (Care Garden) — Species-specific icons fill with color as tasks complete. Dogs fill paw prints, cats wind yarn balls, fish create rising bubbles. When all tasks complete, a spectacular Full Bloom celebration with rose gold particles rewards the user.

Innovation 2: Gamified Achievements (Streaks & Badges) — Individual task streaks with visual badges at milestones (7-day Bronze through 365-day Legend). Missing one task doesn't destroy all progress, reducing anxiety while encouraging consistency.

Innovation 3: Emotional Connection (Live Mood Avatar) — Animated avatar changes mood AUTOMATICALLY based on task completion. Happy when tasks done, Waiting when tasks due, Sad when overdue, Sleeping at night. No manual input required. Creates genuine emotional pull to complete care.

Innovation 4: Auto-Generated Life Story (Pet Legacy Timeline) — Every task, photo, vet visit, and milestone captured automatically in a scrollable timeline. Years of memories without manual journaling. Becomes memorial with PDF export when pet passes.

Innovation 5: Celebration-as-Care (Party Kits) — PoshPet's core differentiator. Guided celebration experiences with Time Capsule voice/video messages (sealed 1 year), Living Memory Pages that grow across years, Care Circle family contributions, intelligent AI pacing, and Legacy Archives that become memorial keepsakes.

Innovation 6: Private Social Accountability (Care Circles) — Private groups of 5-20 invited members sharing progress, photos, milestones. Contribute to each other's Party Kit celebrations. Social support without public exposure.

1.4 Phase 1 Features (11 Total)

CORE PLANNER (5 features)

1. Daily Planner & Calendar View — Central hub with Today/Calendar/Health tabs
2. Care Garden Visualization — Species-specific visual progress with 6 icon styles
3. Task Streak Badges — Individual task streaks with 6 badge tiers
4. Health Tracking (3 Logs) — Weight, vet visits, medications (observation only)
5. Custom Trackers — 10 pre-made templates + custom creation

SIGNATURE FEATURES (3 features)

6. Photo Gallery — 3/day free, unlimited paid, auto-logged to timeline
7. Interactive Avatar + 4 Mood States — Automatic mood changes for 4 animated species
8. Pet Legacy Timeline — Auto-generated life story with Memorial Mode and PDF export

CORE DIFFERENTIATOR + SOCIAL (2 features)

9. Care Circles — Private groups (5-20 members) with Party Kit contribution integration
10. Party Kits — Celebration experiences with Time Capsules, Living Memory Pages, AI pacing

SYSTEM & ADMIN (5 features)

11. Smart Notification System — Intelligent reminders with quiet hours
12. Pet Selector / Multi-Pet Support — Unlimited pets for premium
13. Planner Customization — Show/hide modules, preset themes
14. Admin Panel — Solo founder management interface
15. Invisible AI — Behind-the-scenes optimization (never user-facing)

1.5 Supported Species (14 Total)

Animated Species (Full Mood States)	Static Species (Illustrated Avatar + CSS Breathing)
1. Dogs — 4 Lottie animations (Happy, Waiting, Sad, Sleeping)	5. Rabbits
2. Cats — 4 Lottie animations	6. Guinea Pigs
3. Fish — 4 Lottie animations	7. Hamsters

4. Birds — 4 Lottie animations	8. Ferrets
	9. Chinchillas
	10. Hedgehogs
Total: 16 Lottie animation files	11. Bearded Dragons
	12. Leopard Geckos
	13. Snakes
	14. Turtles/Tortoises

Note: Additional species can receive mood animations in future phases based on user demand and species popularity.

1.6 Free vs Paid Tier Comparison

Feature	Free Tier	PoshPet Society (\$14.99/mo)
Pets per account	1 pet	Unlimited
Daily Planner + Calendar	Full access	Full access
Care Garden + Avatar	Full access	Full access
Task Streak Badges	Full access	Full access
Health Tracking (3 logs)	Full access	Full access
Pet Legacy Timeline	Full access	Full access
Custom Trackers	3 maximum	Unlimited
Photo uploads per day	3 photos	Unlimited
Care Circles	Join only	Create + Join
Party Kits	Basic checklist	Full: Time Capsules, Living Pages, AI pacing
Timeline PDF export	Not available	Available
Garden Decor unlocks	Not available	Available
Planner themes	Default only	4 preset themes
Invisible AI optimization	Basic timing	Full intelligence

PART 2: TECHNOLOGY STACK

2.1 Frontend

Mobile: React Native 0.73+

Language: TypeScript (strict mode)
State Management: Redux Toolkit or Zustand
Navigation: React Navigation 6.x (stack, tab, modal navigators)
Animations: Lottie React Native (avatars, icons), Reanimated 3.x (UI transitions)
HTTP Client: Axios with JWT token interceptors
Forms: React Hook Form + Zod validation
Camera: react-native-image-picker
Push Notifications: @react-native-firebase/messaging
Haptics: react-native-haptic-feedback (task completion)
Audio Recording: react-native-audio-recorder-player (Time Capsule voice memos)
Video Recording: react-native-camera (Time Capsule video messages)

Web: React 18+ with Vite

Build Tool: Vite (fast dev builds, optimized production)
Styling: Tailwind CSS with custom brand config + CSS modules
Animations: Lottie Web (avatars), Framer Motion (UI transitions)
Responsive: Mobile-first with breakpoints at 768px (tablet), 1024px (desktop)

2.2 Backend

Recommended: Node.js + Express + TypeScript

Runtime: Node.js 20 LTS
Framework: Express 4.x with cors, helmet, compression, morgan middleware
ORM: Prisma 5.x for type-safe database queries and migrations
Validation: Zod schemas shared between frontend and backend
Testing: Jest (unit), Supertest (API integration)
Alternative: Python + FastAPI if team prefers Python or anticipates heavy ML features later.

2.3 Database & Storage

PostgreSQL 15+

Primary database for all application data (30+ tables in Phase 1)
UUID primary keys (no sequential IDs exposed)
TIMESTAMP WITH TIME ZONE for all date/time fields
JSONB columns for flexible metadata (kit responses, Memory Page data)
Indexes on all foreign keys and frequently queried columns
Daily automated backups with 30-day retention, point-in-time recovery enabled

File Storage: AWS S3 or Cloudflare R2

Photos: 3 sizes per upload — Thumbnail (200×200px), Medium (800×800px), Original (EXIF stripped)

Time Capsule Media: Voice memos (MP3, 128kbps, 30s max) and Videos (MP4, 720p, 30s max)

Time Capsule Encryption: AES-256 at rest, separate bucket with restricted access policies

Animations: Lottie JSON files served via CDN for fast global loading

Access: Signed URLs with 1-hour expiry

Redis Caching

Session data: JWT refresh tokens (7-day TTL)

API caching: Garden state (60s TTL), streak data (60s TTL), avatar mood (5-min TTL)

Rate limiting: Token bucket, 100 requests/min per user

Time Capsule delivery queue: Scheduled jobs for capsule delivery checks

2.4 Authentication & Payments

Authentication (Choose One)

Option	Strengths	Considerations
Supabase Auth (Recommended)	Built-in email/social/magic links, integrates with PostgreSQL, row-level security	Simplest option for solo developer
Firebase Auth	Excellent mobile SDK, easy push notification integration	More setup for PostgreSQL sync
Auth0	Enterprise-grade, most flexible	Higher cost, more complexity

All options must support: Email/password, Apple Sign-In (required for iOS), Google Sign-In. JWT tokens: 15-minute access, 7-day refresh. Password hashing: Bcrypt 12+ rounds.

Payments: Stripe

Plan	Price	Apple/Google Take (15%)	Your Net
Free	\$0/month	—	—
Monthly	\$14.99/month	\$2.25	\$12.74/month
Annual	\$149.99/year	\$22.50	\$127.49/year

Required Stripe Webhooks: customer.subscription.created, customer.subscription.updated, customer.subscription.deleted, invoice.payment_failed, invoice.payment_succeeded

Grace period: 3 days for failed payments before feature downgrade.

2.5 Infrastructure & Hosting

Recommended stack optimized for solo founder with growth path:

Web Frontend: Vercel (automatic deploys, global CDN)

Mobile: Expo EAS or traditional App Store / Play Store deployment

API Server: Railway or Render (simple deployment, auto-scaling)

Database: Supabase (managed PostgreSQL) or Railway PostgreSQL

Redis: Upstash (serverless) or Railway Redis

File Storage: Cloudflare R2 (S3-compatible, cheaper egress)

Monitoring: Sentry for error tracking

Analytics: Mixpanel or Amplitude for product analytics

Service	Free Tier	At 1,000 Users	At 10,000 Users
Vercel	\$0	\$20/mo	\$20/mo
Railway/Render	\$0-5/mo	\$20/mo	\$50/mo
Supabase (DB)	\$0	\$25/mo	\$75/mo
Upstash (Redis)	\$0	\$10/mo	\$30/mo
Cloudflare R2	\$0	\$5/mo	\$25/mo
Sentry	\$0	\$26/mo	\$26/mo
TOTAL	\$0-5/mo	~\$106/mo	~\$226/mo

PART 3: DESIGN SYSTEM

3.1 Brand Identity

PoshPet combines luxury spa aesthetics with modern productivity design. The visual language evokes a high-end wellness retreat while maintaining the functionality of a productivity app. Think Calm + Notion + Duolingo for pet parents. Watercolor-inspired illustrations, soft rounded edges (minimum 8px border radius), generous white space (minimum 16px between elements), elegant serif + clean sans-serif pairing, and silk-smooth animations. Premium without pretension.

3.2 Color Palette

Primary Colors

Color	Hex	Usage
Cream	#F5F5DC	Backgrounds, cards, overlays
Teal	#008B8B	Primary actions, completed tasks, headings, links
Gold	#FFD700	Celebrations, achievements, premium badges, Full Bloom
Peach	#FFDAB9	Warm accents, secondary buttons, hover states

Secondary Colors

Color	Hex	Usage
Soft Rose	#FFE4E1	Party Kit celebrations, Memory Pages
Sage Green	#9DC183	Health tracking, nature elements, success
Warm Gray	#A9A9A9	Disabled states, secondary text, borders
Charcoal	#333333	Primary body text
White	#FFFFFF	Card backgrounds, input fields

Semantic: Success = Teal (#008B8B), Warning = Gold (#FFD700), Error = Soft coral (#E57373, use sparingly), Info = Teal at 60% opacity

3.3 Typography

Headlines: Canela (elegant serif). Fallback: Cormorant Garamond (free Google Font). Weights: Regular 400, Medium 500. Used for page titles, section headers, celebration text, Memory Page messages.

Body: GT America (clean sans-serif). Fallback: Inter (free Google Font). Weights: Regular 400, Medium 500, Bold 700. Used for body text, labels, buttons, navigation.

Element	Size	Weight	Line Height	Usage
H1	32px	Bold	1.2	Page titles

H2	24px	Bold	1.2	Section headers
H3	20px	Medium	1.3	Subsection headers
H4	18px	Medium	1.3	Card titles
Body	16px	Regular	1.5	Paragraphs, descriptions
Body Small	14px	Regular	1.5	Secondary text, captions
Caption	12px	Regular	1.4	Timestamps, labels
Button	16px	Medium	1.0	Button text

3.4 Spacing & Animation

Base unit: 8px. All spacing values are multiples of 8: XXS (4px), XS (8px), S (16px), M (24px), L (32px), XL (48px), XXL (64px).

Animation Timing Standards

Category	Duration	Examples
Micro	200-300ms	Button press, hover, toggle switch
Standard	400-500ms	Screen transitions, modal open/close, card expand
Complex	600-800ms	Garden icon fill, avatar mood change, badge unlock
Celebration	2-5 seconds	Full Bloom, badge milestone, kit step complete
Cinematic	8-12 seconds	Party Kit completion, Memory Page reveal, Time Capsule seal/unseal

Easing: Standard = cubic-bezier(0.4, 0.0, 0.2, 1). Ease-in = cubic-bezier(0.4, 0.0, 1, 1) for exits. Ease-out = cubic-bezier(0.0, 0.0, 0.2, 1) for entrances. Spring physics for bouncy celebrations.

Performance: 60fps target on all devices. Always respect prefers-reduced-motion. Provide static alternatives for all animations.

3.5 Component Standards

Buttons: Primary (teal bg, white text), Secondary (white bg, teal border), Ghost (transparent, teal text). All: 8px border radius, 44×44px minimum touch target, 12px vertical / 24px horizontal padding. Press: scale to 0.96 with 200ms spring back.

Cards: White (#FFFFFF) background, 12px border radius, shadow 0 2px 8px rgba(0,0,0,0.08), 16px padding (mobile) / 24px (tablet+), 16px margin between cards.

Input Fields: 48px minimum height, 1px solid #E0E0E0 border (2px teal on focus), 8px border radius, label above field in 14px medium weight.

3.6 Accessibility (WCAG 2.1 AA)

Color contrast: Minimum 4.5:1 for normal text, 3:1 for large text

Touch targets: Minimum 44×44px for all interactive elements

Keyboard navigation: All interactive elements tabbable with visible focus ring (2px teal)

Screen readers: Semantic HTML, ARIA labels where needed

Motion: Respect prefers-reduced-motion media query

Text scaling: Support up to 200% zoom without layout breaking

PART 4: ROADMAP & EXCLUSIONS

This document specifies Phase 1 only. Future phases depend on user feedback, retention data, and revenue validation. This section provides roadmap context for architectural decisions.

4.1 Phase 2: Service Provider Marketplace

Timeline: 3-6 months after Phase 1 launch. Adds veterinarian, dog walker, groomer, trainer, and pet sitter booking with in-app scheduling, GPS tracking, payment processing, and automatic timeline logging. Provider profiles with reviews and ratings. International expansion to UK, Canada, Australia.

Progression criteria: 1,000+ paying subscribers, 70%+ DAU rate, <5% monthly churn, 4.5+ App Store rating, Phase 1 stable (<1% crash rate).

4.2 Phase 3: Boutique Marketplace

Timeline: 6-12 months after Phase 2. Curated premium pet products (affiliate/commission model, not inventory-based). Provider-recommended products. Optional subscription boxes. Progression criteria: 5,000+ subscribers, active provider network, expanded team (3+ developers).

4.3 Permanently Excluded

HEALTH FEATURES (Never): Medical diagnosis, AI health recommendations, symptom interpretation, predictive health alerts, connected monitoring devices. Health tracking remains observation-only logging. PoshPet connects users to professionals; it does not replace them.

COMPLEX SOCIAL (Never): Public profiles/feeds, following other users, public comments/forums, pet-to-pet social matching, influencer programs. PoshPet is a luxury care planner with private sharing, not a pet social network. Care Circles provide social connection without the toxicity of public feeds.

ENTERPRISE (Never): Multi-user business accounts, vet clinic integrations, white-label solutions, third-party API access. PoshPet serves individual pet parents, not businesses.

DOCUMENT MAP: COMPLETE SPECIFICATION

The complete PoshPet Phase 1 Technical Documentation spans 5 documents totaling approximately 120 pages. This Foundation document (Document 1) provides the project overview, technology decisions, design system, and roadmap. The remaining documents contain detailed feature specifications.

Document	Contents	Pages
Doc 1: Foundation (this document)	Project Overview, Tech Stack, Design System, Roadmap	~15
Doc 2: Core Features	Care Garden, Streak Badges, Health Tracking, Custom Trackers, Photo Gallery, Avatar + Moods, Timeline	~45
Doc 3: Social, Planner & System	Care Circles, Transitions, Daily Planner, Notifications, Pet Selector, Customization, Admin Panel, Invisible AI, Exclusions	~25
Doc 4: Party Kits	Complete Party Kit specification: Time Capsules, Living Memory Pages, Circle Contributions, Intelligent Pacing, Cinematic Completion, Legacy Archive, all 4 kits	~40
Doc 5: Legal & Architecture	Legal/Compliance, Medical Disclaimers, GDPR/CCPA, Technical Architecture, all database schemas, all API endpoints, cron jobs, deployment	~16

Recommended reading order for developers: Start with this Foundation document for context, then Doc 5 (architecture) for the technical foundation, then build features in order: Doc 2 (core features first), Doc 3 (system features), Doc 4 (Party Kits last, as they integrate with everything else).

POSHPET

Phase 1 Technical Documentation

Document 2 of 5: Core Features

Care Garden | Streak Badges | Health Tracking | Custom Trackers
Photo Gallery | Interactive Avatar | Pet Legacy Timeline

Version 3.0 | February 2026

5.1 CARE GARDEN VISUALIZATION

The Care Garden is a species-specific visual progress tracker that transforms task checkboxes into a beautiful, rewarding visual experience. As users complete daily tasks, icons fill with color in satisfying animations. When all tasks are complete, a spectacular Full Bloom celebration rewards the user's devotion.

5.1.1 Screen Layout & Positioning

Where Care Garden Appears:

Location: Top of Daily Planner screen, directly below the pet avatar (200×200px). The garden sits in a horizontal strip spanning full screen width.

Height: 80px total strip height with 20px left and right padding from screen edges.

Background: Cream (#F5F5DC) with subtle inner shadow at top edge creating depth effect.

Border: None visible; blends seamlessly with planner background.

Z-index: Above task list, below avatar.

Icon Arrangement:

Icons display in a horizontal row, evenly distributed across the strip width. Maximum 6 icons visible without scrolling on mobile (375px width). If more than 6 tasks exist, horizontal scroll is enabled with momentum physics and subtle dot indicators below showing current scroll position.

Icon size: 48×48 pixels on mobile, 60×60 pixels on tablet. **Spacing between icons:** 16px minimum gap. **Vertical centering** within 80px strip height. **Touch target:** 56×56px (extends beyond visible icon area for easier tapping).

Visual Hierarchy:

The garden strip is visually prominent but not overwhelming. It sits between the avatar (emotional focus) and the task list (action focus), creating a visual progress bar effect without being a literal progress bar. Empty icons draw attention to incomplete tasks. Filled icons provide satisfaction. The garden tells the story of today's care at a glance.

5.1.2 Icon States — Three Distinct Visual States

STATE 1: EMPTY (Task Not Complete)

Shape: Species-specific outline only (paw, yarn ball, bubble cluster, etc.)

Stroke: 2px, Gray (#CCCCCC). **Fill:** Completely transparent.

Animation: Static—no animation while empty. On web: subtle hover lightens outline to #DDDDDD.

Emotional Intent: Should look 'waiting to be filled'—inviting action, not depressing. Gray contrast with vibrant teal when filled creates visual pull.

STATE 2: FILLING (Animation In Progress)

Shape: Same species-specific shape.

Fill Color: Teal (#008B8B) rising from bottom to top in 'liquid pouring' effect.

Outline Transition: Gray (#CCCCCC) transitions to teal (#008B8B) as fill reaches it.

Fill Line: Subtle gradient creating liquid surface effect at the fill boundary.

Duration: 600 milliseconds total.

Easing: cubic-bezier(0.4, 0.0, 0.2, 1) — smooth deceleration.

Fill Direction: Bottom to top (like liquid rising in a container).

Overshoot: At 100% fill, icon scales to 1.05x briefly (satisfying pop), then settles to 1.0x over 200ms.

Frame Rate: 60fps for smooth animation.

Trigger: Fires immediately when user completes associated task via long-press (1.5s). Task card slides off screen to right (400ms) while garden icon fill begins simultaneously. Haptic feedback fires at moment of completion.

STATE 3: COMPLETE (Task Done)

Shape: Fully filled species-specific shape.

Fill: Solid teal (#008B8B). Outline matches fill (barely visible).

Glow: Soft outer glow—4px radius, white (#FFFFFF) or cream (#F5F5DC), 40% opacity.

Idle Animation: Subtle pulse every 2 seconds (scale 1.0 to 1.02 and back, 1-second cycle, smooth sine wave). Creates 'alive' feeling without being distracting.

5.1.3 Species-Specific Icons (6 Styles)

DOGS — Paw Prints

Shape: Classic dog paw print (4 toe pads + main pad). Simple, recognizable silhouette.

Empty: Gray outline of paw shape, transparent fill.

Filling: Teal liquid rises from bottom to top over 600ms with slight liquid-surface wobble physics.

Complete: Full teal with soft white glow, gentle pulse every 2 seconds.

Overshoot: At 100%, paw print bounces (scale 1.05x then settles).

CATS — Yarn Balls

Shape: Spherical yarn ball with visible thread texture lines crossing the surface.

Empty: Gray sphere outline with faint yarn texture.

Filling: Colored yarn winds around sphere in spiral motion, rotating 90° during 600ms fill.

Complete: Colorful ball with gold/peach gradient, gentle bounce wobble animation as if ready to roll.

FISH — Bubbles

Shape: Cluster of 3 bubbles (large, medium, small) arranged vertically.

Empty: No bubbles visible—just empty circular outlines.

Filling: Bubbles rise sequentially from bottom with wobble physics. Large bubble first, medium 100ms later, small 200ms later. Each bubble has slight horizontal drift.

Complete: 3 bubbles float with ambient up-down motion (3-second loop) and occasional subtle shine reflections.

BIRDS — Feathers

Shape: 3 overlapping feathers arranged in a fan pattern with barb detail on edges.

Empty: No feathers visible—faint outline placeholders.

Filling: 3 feathers drift down with gentle side-to-side sway and slight rotation. Each feather arrives 100ms apart.

Complete: Feathers rest at bottom with iridescent shimmer effect traveling down the shaft on a 3-second loop.

REPTILES — Scales

Shape: Cluster of 7 diamond/hexagonal scales in interlocking geometric pattern.

Empty: Gray matte diamond scales in cluster.

Filling: Scales gain iridescent shimmer one by one in sequence. Color transitions through gray → green → blue → purple → gold.

Complete: Rainbow shimmer continuously cycling across all scales, metallic appearance with slow color shift on 5-second loop.

DEFAULT (Rabbits, Guinea Pigs, Hamsters, Ferrets, Chinchillas, Hedgehogs, Turtles) — Flowers

Shape: Simple 5-petal flower with stem.

Empty: Small green seedling (2 tiny leaves, minimal stem).

Filling: Time-lapse growth effect over 800ms. Stem grows upward, leaves unfurl, bud appears at top, petals open outward.

Complete: Full bloom flower (pink/peach watercolor tones) swaying gently as if in light breeze. 3-second sway loop.

5.1.4 Full Bloom Celebration

When ALL daily tasks are complete, trigger the Full Bloom celebration:

Animation Sequence (3 seconds total):

0.0s: All garden icons pulse simultaneously (scale 1.0 → 1.15)

0.3s: Rose gold particles begin rising from each icon (20-30 particles per icon, 4-8px diameter)

0.5s: Icons float upward slightly (15px lift with ease-out)

0.8s: Soft golden glow spreads as radial gradient behind all icons

1.0s: Celebration text fades in center: 'Full Bloom!' in Canela serif, 28px, Gold (#FFD700), scale 0.9 → 1.0

1.5s: Confetti particles burst outward from center

2.0s: Gentle chime sound plays (800ms duration, 50% system volume, if sound enabled)

2.5s: Animation begins settling—particles fade, text starts dissolving

3.0s: Complete. Icons return to calm completed state with slightly enhanced glow for remainder of day.

Particle Specifications:

Particle count: 20-30 rose gold particles per icon. Size: 4-8px diameter varying randomly. Color: Rose gold gradient (#FFD700 to #FFDAB9). Motion: Rise with slight horizontal drift, fade to 0% opacity at top of screen.

Celebration Logging:

Full Bloom achievement is logged to Pet Legacy Timeline with entry: 'Full Bloom achieved! All [X] tasks completed.' Includes garden snapshot image capture for the timeline event card. Timestamp and total task count stored.

5.1.5 Unlockable Garden Decor (Premium Only)

Premium users unlock decorative garden elements at streak milestones:

7-day streak: Basic border styles unlocked (Vine, Floral, Minimal gold line, Ornate scrollwork corners)

30-day streak: Seasonal backgrounds unlocked (Spring cherry blossoms, Summer sun rays, Autumn falling leaves, Winter gentle snowflakes)

100-day streak: Animated ambient effects unlocked (Floating petals, Gentle rain, Snow, Butterflies crossing)

365-day streak: Premium particle effects unlocked (enhanced celebration visuals)

Users select active decor from unlocked options in Settings. One border, one background, and one ambient effect can be active simultaneously. All decor is cosmetic and does not affect functionality.

5.1.6 Database Schema

```
CREATE TABLE garden_state (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  date DATE NOT NULL,
  total_tasks INTEGER NOT NULL DEFAULT 0,
  completed_tasks INTEGER NOT NULL DEFAULT 0,
  full_bloom_achieved BOOLEAN DEFAULT FALSE,
  full_bloom_achieved_at TIMESTAMP WITH TIME ZONE,
  snapshot_url VARCHAR(500),
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  updated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  UNIQUE(user_id, pet_id, date)
);

CREATE TABLE garden_decor_unlocks (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  decor_type VARCHAR(50) NOT NULL, -- 'border', 'background', 'ambient'
  decor_id VARCHAR(50) NOT NULL, -- 'vine', 'spring', 'butterflies', etc.
  unlocked_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
```

```

    UNIQUE(user_id, decor_type, decor_id)
);

CREATE TABLE garden_preferences (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  active_border VARCHAR(50),
  active_background VARCHAR(50),
  active_ambient VARCHAR(50),
  UNIQUE(user_id, pet_id)
);

```

5.1.7 API Endpoints

Method	Endpoint	Description	Auth
GET	/api/garden/{pet_id}/today	Get today's garden state (tasks, completion, bloom status)	Required
GET	/api/garden/{pet_id}/history?days=30	Get garden history for calendar view (bloom days)	Required
POST	/api/garden/{pet_id}/full-bloom	Log Full Bloom achievement, trigger snapshot	Required
GET	/api/garden/decor	Get all unlocked decor items for user	Required
GET	/api/garden/decor/available	Get available decor with unlock requirements	Required
PUT	/api/garden/{pet_id}/decor	Set active border, background, ambient	Premium

5.1.8 Required Animation Files

File Name	Description	Duration	Max Size
garden_dog_paw_fill.json	Paw print liquid fill animation	600ms	200KB
garden_cat_yarn_fill.json	Yarn ball winding animation	600ms	200KB
garden_fish_bubble_fill.json	Bubble rise animation (3 bubbles)	600ms	200KB
garden_bird_feather_fill.json	Feather drift-down animation (3 feathers)	600ms	200KB
garden_reptile_scale_fill.json	Scale shimmer animation (7 scales)	600ms	200KB
garden_default_flower_fill.json	Seedling-to-bloom growth animation	800ms	200KB
garden_full_bloom.json	Full Bloom celebration (particles, glow, text)	3000ms	500KB

5.2 TASK STREAK BADGES

Task Streak Badges track consecutive completion of individual tasks. Each task has its own independent streak counter. This is intentional: missing one task doesn't destroy all progress. A user who misses a walk still keeps their feeding streak. This reduces anxiety and encourages consistent effort without perfectionism.

5.2.1 Badge Tier System

Tier	Days	Badge Name	Visual Description	Unlock Message
1	7	Bronze Paw	Matte bronze paw print, warm brown tones, subtle shadow	'One week of devoted care!'
2	14	Silver Paw	Polished silver paw, soft reflective shine animation	'Two weeks strong!'
3	30	Gold Paw	Gleaming gold paw, sparkle burst every 4 seconds	'A month of love!'
4	60	Diamond Paw	Crystal paw with rainbow light refraction, 5s shimmer cycle	'Two months of dedication!'
5	100	Platinum Crown	Platinum paw with floating crown above, 2s float loop	'100 days of devotion!'
6	365	Legend Star	Golden star with eternal flame, 1s flicker loop	'A full year of love!'

5.2.2 Badge Display Specifications

Location on Task Card:

Position: Bottom-right corner of each task card in Daily Planner. Size: 24×24px on mobile, 28×28px on tablet. Background: Circular white background with subtle drop shadow. Each task shows its own badge independently—a user might have Gold on 'Walk' and Bronze on 'Brush' simultaneously.

Badge Detail View:

Mobile tap on badge: Brief bottom sheet slides up showing streak count, badge tier, task name, and 'started on' date. Web hover: Tooltip with same info. Badge icon does subtle bounce when interacted with.

Badge Animations:

Bronze/Silver: Static with subtle shadow (no animation). Gold: Small sparkle burst every 4 seconds (3-4 tiny stars). Diamond: Rainbow shimmer cycles continuously on 5-second loop. Platinum Crown: Crown floats gently up/down on 2-second loop (2px movement). Legend Star: Flame flickers continuously on 1-second loop.

5.2.3 Streak Calculation Rules

Increment: Streak increases by 1 when task completed before midnight in user's local timezone.

Reset: Streak resets to 0 if task is not completed for a full calendar day.

Grace Period: None—strict daily requirement maintains achievement value.

Multiple completions: Only first completion per day counts toward streak.

Backdating: Cannot backdate completions to save broken streaks.

Timezone: Uses user's current timezone at moment of completion.

Skip Functionality

Users can mark a task as 'Skip today' instead of completing it. Skipping PAUSES the streak (does not reset). Maximum 3 consecutive skip days before streak resets. Optional skip reason: Vacation, Sick, Weather, Other. Skipped days do not count toward streak total. Use case: traveling, sick days, weather prevents outdoor activities.

5.2.4 Milestone Celebrations

Celebration Sequence (2.5 seconds):

0.0s: Screen dims slightly (30% black overlay)

0.3s: Badge icon enters from bottom, scaling up from 0 to full size

0.6s: Badge reaches center screen, particles burst outward in circle

1.0s: Badge name appears below: 'Gold Paw!' in Canela serif

1.5s: Streak count: '30 Days!' with task name below

2.0s: 'Share' and 'Close' buttons fade in at bottom

Sound: Ascending triumphant chime (3 notes)

Share Image Generation:

Generate 1080×1080px shareable image containing: badge icon, streak count, pet avatar, task name, PoshPet branding (subtle bottom corner). Share targets: Instagram Stories, Facebook, Twitter/X, Save to Camera Roll.

Timeline Integration:

Every badge unlock logged to Pet Legacy Timeline. Entry format: 'Achieved [X]-day [Task Name] streak! [Badge Name] Badge unlocked.' Badge icon displayed in timeline event card.

5.2.5 Database Schema

```
CREATE TABLE task_streaks (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  task_template_id UUID NOT NULL REFERENCES task_templates(id) ON DELETE CASCADE,
  current_streak INTEGER NOT NULL DEFAULT 0,
  longest_streak INTEGER NOT NULL DEFAULT 0,
  current_badge_tier INTEGER NOT NULL DEFAULT 0,
  last_completed_date DATE,
```

```

    streak_started_at DATE,
    consecutive_skips INTEGER DEFAULT 0,
    updated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
    UNIQUE(user_id, pet_id, task_template_id)
);

CREATE TABLE streak_milestones (
    id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
    user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
    pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
    task_template_id UUID NOT NULL REFERENCES task_templates(id),
    badge_tier INTEGER NOT NULL,
    streak_count INTEGER NOT NULL,
    achieved_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
    share_image_url VARCHAR(500)
);

```

5.2.6 API Endpoints

Method	Endpoint	Description
GET	/api/streaks/{pet_id}	Get all active streaks for a pet
GET	/api/streaks/{pet_id}/{task_id}	Get specific task streak details
POST	/api/streaks/{pet_id}/{task_id}/skip	Mark task as skipped today (pauses streak)
GET	/api/streaks/{pet_id}/milestones	Get all milestone achievements for a pet
POST	/api/streaks/share-image	Generate shareable image for a milestone

5.3 HEALTH TRACKING (3 Logs)

Health Tracking provides three observation-only logging systems. These are NOT diagnostic tools and do NOT provide medical advice. All health features include prominent disclaimers directing users to consult licensed veterinarians.

5.3.1 Weight Log

Purpose: Track pet weight over time with visual trend indicators for personal observation.

Input Fields

Weight value: Numeric input with 0.1 precision (e.g., 45.2). **Unit:** lbs or kg (user preference, persists across sessions). **Date:** Defaults to today, past dates selectable via date picker. **Notes:** Optional, 200 characters max. **Time:** Optional, defaults to current time.

Visual Display

Latest weight shown prominently at top of Weight Log screen in large text (32px, bold, teal). Trend arrow displayed beside weight: ↑ up (gained 2%+), ↓ down (lost 2%+), → stable (within 2%). Trend calculated by comparing to previous entry.

Line chart showing last 12 entries. Chart X-axis: dates (auto-scaled). Chart Y-axis: weight values (auto-scaled with 10% padding above/below range). Line color: Teal (#008B8B), 2px width. Data points: Small teal circles (8px), tap to see exact value tooltip. Chart background: Cream (#F5F5DC). Chart height: 200px on mobile.

Timeline Integration

Each weight entry creates timeline event: "Weight logged: [value] [unit] [trend arrow]". Notes included if provided.

5.3.2 Vet Visit Log

Purpose: Record veterinary appointments for personal reference and history tracking.

Input Fields

Date of visit: Date picker (required)

Clinic name: Text input with autocomplete from previous entries (required)

Visit type: Dropdown selection (required): Wellness/Annual Checkup, Sick Visit, Emergency, Dental, Surgery, Vaccination, Follow-up, Other

Reason: Text input, 500 characters max (required)

Outcome/Notes: Text area, 1000 characters max (optional)

Follow-up needed: Yes/No toggle

Follow-up date: Date picker (appears if Follow-up = Yes)

Cost: Numeric input (optional, personal tracking)

Attachments: Upload up to 5 images (receipts, records, photos). Max 10MB each, JPEG/PNG/HEIC.

List View

Reverse chronological (most recent first). Each entry card shows: date, clinic name, visit type badge (color-coded), reason (truncated to 2 lines). Follow-up indicator icon if scheduled. Tap card to view full details with all fields and attachments.

Timeline Integration

Creates event: 'Visited [Clinic Name] for [Visit Type]: [Reason]'. Attachment thumbnails shown if present.

5.3.3 Medication Log

Purpose: Track medication schedules and administration for personal records.

Medication Setup Fields

Name: Text input (required)

Dosage: Text input (e.g., '1 tablet', '0.5ml', '10mg')

Frequency: Dropdown: Once daily, Twice daily, Three times daily, Every other day, Weekly, As needed, Other (custom schedule)

Start date: Date picker

End date: Date picker (optional, for limited courses)

Prescribing vet: Text input (optional)

Notes: Text area, 500 characters max

Reminder: Toggle to create Daily Planner task for each dose

Administration Tracking

Each dose can be marked as: 'Given' (default), 'Skipped' (with optional reason), or 'Refused' (pet wouldn't take it). Each administration logged with timestamp and optional notes field. History view shows all administrations in reverse chronological order. Export as PDF available for sharing with veterinarian.

Timeline Integration

Each administration creates event: '[Medication name] administered' with dosage info.

5.3.4 REQUIRED Medical Disclaimer

The following disclaimer MUST appear on EVERY health tracking screen:

'PoshPet Health Tracking is for personal observation and record-keeping only. It does not provide medical advice, diagnosis, or treatment recommendations. Always consult a licensed veterinarian for any health concerns about your pet. In case of emergency, contact your vet or emergency animal hospital immediately.'

Placement Requirements:

Weight Log: Below chart, above entry form

Vet Visit Log: At top of list view in a subtle info banner

Medication Log: Below medication list, above add button

First-time use: Full-screen acknowledgment modal required before accessing ANY health feature. User must tap 'I Understand' to proceed. Acceptance stored and not shown again.

5.3.5 Database Schema

```
CREATE TABLE weight_logs (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  weight_value DECIMAL(6,2) NOT NULL,
  weight_unit VARCHAR(3) NOT NULL DEFAULT 'lbs',
  logged_date DATE NOT NULL,
  logged_time TIME,
  notes VARCHAR(200),
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE INDEX idx_weight_pet_date ON weight_logs(pet_id, logged_date DESC);

CREATE TABLE vet_visits (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  visit_date DATE NOT NULL,
  clinic_name VARCHAR(200) NOT NULL,
  visit_type VARCHAR(50) NOT NULL,
  reason VARCHAR(500) NOT NULL,
  outcome VARCHAR(1000),
  cost DECIMAL(10,2),
  follow_up_needed BOOLEAN DEFAULT FALSE,
  follow_up_date DATE,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE TABLE vet_visit_attachments (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  vet_visit_id UUID NOT NULL REFERENCES vet_visits(id) ON DELETE CASCADE,
  file_url VARCHAR(500) NOT NULL,
  file_name VARCHAR(200),
  file_type VARCHAR(50),
  uploaded_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE TABLE medications (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  name VARCHAR(200) NOT NULL,
```

```

dosage VARCHAR(100),
frequency VARCHAR(50),
start_date DATE,
end_date DATE,
prescribing_vet VARCHAR(200),
notes VARCHAR(500),
is_active BOOLEAN DEFAULT TRUE,
reminder_enabled BOOLEAN DEFAULT FALSE,
created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE TABLE medication_administrations (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  medication_id UUID NOT NULL REFERENCES medications(id) ON DELETE CASCADE,
  administered_at TIMESTAMP WITH TIME ZONE NOT NULL,
  status VARCHAR(20) NOT NULL DEFAULT 'given', -- 'given', 'skipped',
  'refused'
  notes VARCHAR(200),
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

```

5.3.6 API Endpoints

Method	Endpoint	Description
GET	/api/health/{pet_id}/weight	Get weight log entries (paginated, newest first)
POST	/api/health/{pet_id}/weight	Add new weight entry
DELETE	/api/health/weight/{id}	Delete a weight entry
GET	/api/health/{pet_id}/vet-visits	Get vet visit history (paginated)
POST	/api/health/{pet_id}/vet-visits	Add new vet visit
PUT	/api/health/vet-visits/{id}	Update vet visit details
GET	/api/health/{pet_id}/medications	Get medications list (active first)
POST	/api/health/{pet_id}/medications	Add new medication
PUT	/api/health/medications/{id}	Update medication (mark inactive, edit)
POST	/api/health/medications/{id}/administer	Log dose administration
GET	/api/health/{pet_id}/export	Export all health data as PDF

5.4 CUSTOM TRACKERS

Custom Trackers allow users to track any recurring pet care activity not covered by default tasks.

5.4.1 Pre-Made Templates (10 Total)

Universal Templates (7)

#	Template Name	Default Icon	Default Frequency	Description
1	Brushing/Grooming	Brush	Weekly	Track coat maintenance sessions
2	Nail Trimming	Scissors	Biweekly	Log nail care with optional length notes
3	Teeth Cleaning	Tooth	Daily	Track dental hygiene routine
4	Bath Time	Droplet	Monthly	Record bathing, products used, reactions
5	Training Session	Brain	Daily	Log activities, commands, progress notes
6	Playtime	Ball	Daily	Track play and enrichment activities
7	Outdoor Time	Sun	Daily	Non-walk outdoor time (yard, patio, etc.)

Species-Specific Templates (3)

#	Template Name	For Species	Default Frequency
8	Tank/Cage Cleaning	Fish, Birds, Small Mammals, Reptiles	Weekly
9	Litter Box Cleaning	Cats	Daily
10	Habitat Temperature Check	Reptiles	Daily

5.4.2 Custom Tracker Creation

Input Fields:

Name: Text input, required, 50 characters max

Description: Text input, optional, 200 characters max

Icon: Select from 20 pre-made icons (paw, heart, star, bone, leaf, droplet, sun, moon, pill, brush, scissors, tooth, ball, brain, fish, bird, scale, thermometer, clock, sparkle)

Frequency: Daily, Every X days (2-30), Weekly, Biweekly, Monthly, As needed

Time of day: Morning, Afternoon, Evening, Anytime

Reminder: On/Off toggle. If On, set specific reminder time.

Notes on completion: Enable/disable notes input when marking complete

Streak tracking: Enable/disable (default enabled)

Limits: Free users: 3 custom trackers maximum. Premium users: unlimited. Upgrade prompt shown when free user hits limit.

5.4.3 Database Schema

```
CREATE TABLE custom_trackers (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  name VARCHAR(50) NOT NULL,
  description VARCHAR(200),
  icon VARCHAR(50) NOT NULL DEFAULT 'paw',
  frequency VARCHAR(20) NOT NULL DEFAULT 'daily',
  frequency_value INTEGER,          -- for 'every_x_days' type
  time_of_day VARCHAR(20) DEFAULT 'anytime',
  reminder_enabled BOOLEAN DEFAULT FALSE,
  reminder_time TIME,
  notes_enabled BOOLEAN DEFAULT TRUE,
  streak_enabled BOOLEAN DEFAULT TRUE,
  is_active BOOLEAN DEFAULT TRUE,
  display_order INTEGER DEFAULT 0,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);
```

5.4.4 API Endpoints

Method	Endpoint	Description
GET	/api/trackers/{pet_id}	Get all custom trackers for a pet
POST	/api/trackers/{pet_id}	Create new custom tracker
PUT	/api/trackers/{id}	Update tracker settings
DELETE	/api/trackers/{id}	Delete tracker
POST	/api/trackers/{id}/complete	Mark tracker as completed today
GET	/api/trackers/{id}/history	Get completion history

5.5 PHOTO GALLERY

The Photo Gallery stores and displays pet photos with automatic integration into the Pet Legacy Timeline. Every photo becomes part of the pet's permanent life story.

5.5.1 Upload Specifications

Free users: 3 photos per day per pet

Premium users: Unlimited photos

Max file size: 10MB per photo

Formats: JPEG, PNG, HEIC (HEIC auto-converted to JPEG)

Min resolution: 200×200 pixels

Max resolution: 4096×4096 pixels (larger images downsampled automatically)

5.5.2 Photo Processing Pipeline

When a photo is uploaded, the backend processes it into three versions:

Version	Dimensions	Quality	Usage
Thumbnail	200×200px, cropped square	JPEG 80%	Gallery grid, timeline events, avatar backgrounds
Medium	800×800px, fit within (aspect ratio preserved)	JPEG 85%	Full-screen viewing, Memory Pages, sharing
Original	Full resolution as uploaded	Original quality	Download, high-res export, printing

Additional processing: EXIF data stripped for privacy (all metadata removed). Orientation auto-corrected from EXIF before stripping. Processing time target: under 5 seconds.

5.5.3 Photo Metadata

Caption: Optional, 200 characters max, editable after upload

Date taken: Auto-detected from EXIF or defaults to upload date

Favorite flag: User can mark/unmark photos as favorites

Party Kit link: Photos can be associated with Party Kit celebrations

Circle sharing: User chooses whether photo is shared to their Care Circles

5.5.4 Gallery Views

Grid View (Default)

3 columns on mobile, 4 on tablet, 6 on desktop. Square thumbnails with 8px rounded corners. 4px gap between photos. Favorite photos show heart overlay icon (bottom-right). Infinite scroll loading 50 photos per page. Tap any photo to open full-screen view.

Timeline View

Photos grouped by date with elegant serif date headers (Canela font). Masonry layout allowing varied photo sizes (some span 2 columns). Captions visible below each photo in the timeline layout.

Full-Screen View

Swipe left/right to navigate between photos. Double-tap or pinch to zoom. Caption overlay at bottom (translucent dark background). Top toolbar: Back, Share, Delete, Favorite toggle. Tap photo to show/hide controls. Dark background for photo focus.

5.5.5 Timeline Integration

Every photo upload automatically creates a Timeline event. Event type: 'photo'. Display: Thumbnail preview (120px) with caption text. Tap to open full-screen photo view. Multiple photos uploaded same day are grouped under one date header in the timeline.

5.5.6 Database Schema

```
CREATE TABLE photos (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  original_url VARCHAR(500) NOT NULL,
  thumbnail_url VARCHAR(500) NOT NULL,
  medium_url VARCHAR(500) NOT NULL,
  caption VARCHAR(200),
  taken_at TIMESTAMP WITH TIME ZONE,
  uploaded_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  is_favorite BOOLEAN DEFAULT FALSE,
  shared_to_circles BOOLEAN DEFAULT FALSE,
  party_kit_id UUID REFERENCES user_kit_progress(id) ON DELETE SET NULL,
  width INTEGER,
  height INTEGER
);

CREATE INDEX idx_photos_pet_date ON photos(pet_id, taken_at DESC);
CREATE INDEX idx_photos_favorites ON photos(pet_id, is_favorite) WHERE
is_favorite = TRUE;
```

5.5.7 API Endpoints

Method	Endpoint	Description
GET	/api/photos/{pet_id}?page=1&limit=50	Get photos (paginated, newest first)
GET	/api/photos/{pet_id}/favorites	Get favorited photos only
POST	/api/photos/{pet_id}	Upload new photo (multipart form)
PUT	/api/photos/{id}	Update caption, favorite status
DELETE	/api/photos/{id}	Delete photo and all 3 versions from storage

5.6 INTERACTIVE AVATAR + 4 MOOD STATES

The Interactive Avatar is a signature feature displaying an animated representation of the user's pet with automatic mood changes. No competitor offers automatic mood states tied to care completion. The avatar creates genuine emotional connection that drives daily engagement.

5.6.1 Mood Priority System

The avatar cycles between 4 mood states based on real-time task completion and time of day. Users never manually select mood—the system calculates it automatically.

Priority 1 — SLEEPING: 10 PM – 6 AM local time (overrides everything)

Priority 2 — SAD: Any task overdue 4+ hours (highest daytime priority)

Priority 3 — WAITING: Any task due within 2 hours and not complete

Priority 4 — HAPPY: 80%+ tasks complete, or no pending/overdue tasks

5.6.2 Mood 1: HAPPY

Trigger Conditions:

All daily tasks completed, OR 80%+ tasks completed, OR no tasks due within 2 hours AND no tasks overdue.

Visual Specifications:

Posture: Upright, alert, energetic

Movement: Gentle bounce up/down (3px amplitude, 2-second cycle)

Eyes: Wide open, bright, sparkle animation every 3 seconds (small star burst at eye)

Dogs: Tail wagging side-to-side (30° arc, 0.5-second cycle)

Cats: Slight purring vibration on chest, tail upright and curled

Fish: Active swimming left/right within frame, bubbles rising from mouth

Birds: Occasional wing flutter (every 4 seconds), head bobs side to side

Color saturation: 100% (vibrant, full color)

Optional particles: Subtle sparkles floating around avatar (Premium cosmetic future)

5.6.3 Mood 2: WAITING

Trigger Conditions:

At least one task due within next 2 hours AND that task not yet completed AND no tasks overdue 4+ hours.

Visual Specifications:

Posture: Alert, attentive, looking toward side of screen (toward task list)

Movement: Minimal, occasional head turn toward tasks

Eyes: Wide, watching, slow blink every 4 seconds

Dogs: Ears perked up, tail still or very slow gentle sway

Cats: Ears forward and alert, whiskers spread wide
Fish: Hovering near surface of frame, looking upward expectantly
Birds: Head cocked to one side, alert expression, still on perch
Color saturation: 100% (normal, not muted)
Animation loop: 3-second cycle with subtle anticipatory motion
Emotional intent: Anticipation, not anxiety. Pet is waiting hopefully.

5.6.4 Mood 3: SAD

Trigger Conditions:

At least one task overdue by 4 or more hours. The 4-hour threshold is intentionally high to avoid constant sadness from minor delays.

Visual Specifications:

Posture: Droopy, lowered head, hunched/curled body
Movement: Very slow, minimal energy, heavy breathing
Eyes: Half-closed, looking downward, no sparkle effect
Dogs: Tail lowered and still, ears flat, nose down
Cats: Curled slightly inward, ears rotated back, tail wrapped around body
Fish: Slow sinking motion toward bottom of frame, fins barely moving
Birds: Feathers slightly puffed/ruffled, head tucked toward chest
Color saturation: 85-90% (slightly muted, 10-15% less vibrant. NOT grayscale.)
Animation loop: 4-second cycle, very slow breathing motion
IMPORTANT design note: Sad mood should evoke gentle 'aww' sympathy, not guilt or anxiety. The pet looks like it needs love, not like it's being neglected. This is a critical emotional design distinction.

5.6.5 Mood 4: SLEEPING

Trigger Conditions:

Current time between 10:00 PM and 6:00 AM in user's local timezone. This OVERRIDES all other mood calculations regardless of task status.

Visual Specifications:

Posture: Curled up in sleeping position, peaceful expression
Eyes: Closed, relaxed
Dogs: Curled into ball, nose tucked under tail or paws
Cats: Classic cat loaf position or curled with tail over nose
Fish: Resting at bottom of frame, minimal fin movement, slight sway
Birds: On perch, head tucked under wing, body fluffed
Colors: Soft, warm tones with slight blue night tint (5% blue overlay)
Animation: Gentle breathing (chest rises over 1.5s, falls over 1.5s, 3-second cycle)

Z particles: 3 'Z' letters float upward in sequence. Each Z: starts small, grows slightly, drifts up and right, fades to 0% opacity. Staggered 1.5 seconds apart. 5-second total cycle.

5.6.6 Mood Calculation Algorithm

```
function calculateMood(petId, userTimezone) {
  const now = getCurrentTimeInTimezone(userTimezone);
  const hour = now.getHours();

  // Priority 1: Sleeping (10 PM - 6 AM)
  if (hour >= 22 || hour < 6) return 'sleeping';

  const tasks = getTodaysTasks(petId);
  const completed = tasks.filter(t => t.completed).length;
  const total = tasks.length;

  // Priority 2: Sad (any task overdue 4+ hours)
  const hasOverdue = tasks.some(t => !t.completed && hoursOverdue(t) >= 4);
  if (hasOverdue) return 'sad';

  // Priority 3: Waiting (task due within 2 hours)
  const hasUpcoming = tasks.some(t => !t.completed && hoursTilDue(t) <= 2);
  if (hasUpcoming) return 'waiting';

  // Priority 4: Happy (default positive state)
  return 'happy';
}
```

5.6.7 Species Animation Matrix

Species	Mood Animations	Type	Files
Dogs	YES — Happy, Waiting, Sad, Sleeping	Lottie JSON	4
Cats	YES — Happy, Waiting, Sad, Sleeping	Lottie JSON	4
Fish	YES — Happy, Waiting, Sad, Sleeping	Lottie JSON	4
Birds	YES — Happy, Waiting, Sad, Sleeping	Lottie JSON	4
Rabbits	NO — Single illustrated avatar	SVG/PNG + CSS breathing	1
Guinea Pigs	NO	SVG/PNG + CSS breathing	1

Hamsters	NO	SVG/PNG + CSS breathing	1
Ferrets	NO	SVG/PNG + CSS breathing	1
Chinchillas	NO	SVG/PNG + CSS breathing	1
Hedgehogs	NO	SVG/PNG + CSS breathing	1
Bearded Dragons	NO	SVG/PNG + CSS breathing	1
Leopard Geckos	NO	SVG/PNG + CSS breathing	1
Snakes	NO	SVG/PNG + CSS breathing	1
Turtles/Tortoises	NO	SVG/PNG + CSS breathing	1

Total asset files: 16 Lottie animations + 10 static illustrations = 26 files.

5.6.8 Technical Implementation

Container: 200×200 pixels, top center of Daily Planner below header

Background: Transparent (sits on cream app background)

Mood calculation: Every 5 minutes while app is active

Mood cache: Redis with 5-minute TTL for performance

Mood transition: 500ms crossfade when mood changes

Lottie player: lottie-react-native (mobile), lottie-web (web)

Static fallback: CSS animation for gentle breathing (scale 1.0 to 1.02, 3s cycle)

Reduced motion: Respect prefers-reduced-motion, show static image

File size: Each Lottie file under 500KB for fast loading

Frame rate: 60fps target for smooth animation

5.6.9 Required Animation Files

File Name	Species	Mood	Loop Duration	Max Size
avatar_dog_happy.json	Dog	Happy	2000ms	500KB
avatar_dog_waiting.json	Dog	Waiting	3000ms	500KB
avatar_dog_sad.json	Dog	Sad	4000ms	500KB
avatar_dog_sleeping.json	Dog	Sleeping	3000ms	500KB

avatar_cat_happy.json	Cat	Happy	2000ms	500KB
avatar_cat_waiting.json	Cat	Waiting	3000ms	500KB
avatar_cat_sad.json	Cat	Sad	4000ms	500KB
avatar_cat_sleeping.json	Cat	Sleeping	3000ms	500KB
avatar_fish_happy.json	Fish	Happy	2000ms	500KB
avatar_fish_waiting.json	Fish	Waiting	3000ms	500KB
avatar_fish_sad.json	Fish	Sad	4000ms	500KB
avatar_fish_sleeping.json	Fish	Sleeping	3000ms	500KB
avatar_bird_happy.json	Bird	Happy	2000ms	500KB
avatar_bird_waiting.json	Bird	Waiting	3000ms	500KB
avatar_bird_sad.json	Bird	Sad	4000ms	500KB
avatar_bird_sleeping.json	Bird	Sleeping	3000ms	500KB

5.6.10 Database Schema

```
CREATE TABLE pet_mood_state (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  current_mood VARCHAR(20) NOT NULL DEFAULT 'happy',
  mood_calculated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  task_completion_rate DECIMAL(3,2),
  UNIQUE (pet_id)
);
```

5.7 PET LEGACY TIMELINE

The Pet Legacy Timeline is an auto-generated chronological life story. Every app activity is captured automatically—no manual journaling required. This creates years of preserved memories without extra effort. When a pet passes, the timeline becomes a memorial with PDF export.

5.7.1 Auto-Captured Event Types

The following events are logged automatically with no user action beyond normal app usage:

Event Type	Icon	Auto-Generated Title	Media
task_complete	Checkmark ✓	'[Pet] went for a walk' / '[Pet] had breakfast'	None
photo	Camera	'Photo moment' or user caption	Photo thumbnail
weight	Scale	'Weight: 45.2 lbs ↑' (with trend arrow)	None
vet_visit	Medical +	'Vet visit: [Type] at [Clinic]'	Attachments if any
medication	Pill	'[Med name] administered'	None
streak_milestone	Badge	'30-day Walk streak! Gold Paw!'	Badge image
full_bloom	Flower	'Full Bloom! All [X] tasks completed'	Garden snapshot
party_kit	Gift/Cake	'Birthday Celebration completed!'	Memory Page link
custom_entry	Star	User-written title	Optional photo

5.7.2 Visual Layout

Feed Structure:

Vertical scrolling feed (similar to social media timeline). Timeline spine: vertical teal line (#008B8B) on left side, 2px width, running from top to bottom of feed. Scroll direction: newest at top (default), toggle available for oldest first.

Event Card Design:

Background: White (#FFFFFF). Border radius: 12px. Shadow: 0 2px 8px rgba(0,0,0,0.08). Width: Full width minus 20px margins on each side. Left edge connects to timeline spine with small teal circle (8px diameter).

Card contents: Event icon (32×32px, left side, event-type specific). Event title (bold, 16px). Timestamp (small, gray #666666, below title). Event description if applicable. Photo preview if present (120px height, rounded corners, tap to enlarge).

Date Grouping:

Events grouped by date. Date headers in elegant serif font (Canela or Cormorant Garamond fallback). Format: 'Saturday, February 1, 2026'. Dates separated by increased spacing (32px gap).

5.7.3 Manual Entry

Users can add custom timeline entries alongside auto-generated ones:

Title: Text input, required, 200 characters max

Description: Text area, optional, 500 characters max

Photo: Optional single photo upload

Date: Date picker, defaults to today, past dates allowed

Icon: Select from 12 options (star, heart, paw, bone, plus, flag, pin, note, celebration, milestone, memory, custom)

5.7.4 Category Filters

Horizontal filter bar at top of timeline, scrollable:

All: (default) Shows every event type

Tasks: Only task completions

Health: Weight entries, vet visits, medication administrations

Photos: Photo uploads only

Milestones: Streak badges, Full Blooms, custom milestones

Celebrations: Party Kit completions and Memory Pages

5.7.5 Memorial Mode

When user marks pet as 'passed away,' the timeline transforms into a memorial.

Activation Flow:

Settings > Pet Profile > 'Mark as Passed Away' button. Confirmation modal appears requesting date of passing. Action is significant—requires user to TYPE the pet's name to confirm (prevents accidental activation). Once confirmed, changes are immediate and reversible only through support request.

Visual Transformation:

Header: '[Pet Name] — Forever in our hearts'

Dates: Lifespan displayed: 'March 2015 — January 2026'

Photos: Gentle sepia tone overlay on all photos (CSS filter: sepia(30%))

Photo borders: Soft vignette edges (inner shadow creating gentle frame)

Pet icon: Small angel wings or star icon beside pet name in all references

Task reminders: Immediately stopped for this pet

Daily Planner: Hidden for this pet—Timeline becomes primary view

Avatar: Shows sleeping pose permanently with soft warm glow

Memorial Features:

PDF Export: 'Download Memorial PDF' button prominently displayed (Premium). Generates formatted PDF with all timeline events, photos, milestones. Cover page with pet photo, name, dates. Table of contents by year/month.

Celebration Archive: All Party Kit Memory Pages accessible in dedicated 'Celebrations' tab. Shows: '3 Birthdays Celebrated, 2 Adoption Anniversaries, 1 Welcome.' Each Memory Page preserved permanently.

Time Capsule Release: Any sealed Time Capsules for this pet are released immediately. Notification: 'We have messages waiting for you.' Delivered with extra care—gentle animation, no celebration, just quiet presentation.

5.7.6 Database Schema

```
CREATE TABLE timeline_events (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  event_type VARCHAR(50) NOT NULL,
  title VARCHAR(200) NOT NULL,
  description TEXT,
  icon VARCHAR(50),
  media_url VARCHAR(500),
  media_type VARCHAR(20),
  metadata JSONB, -- flexible storage for event-specific data
  event_date TIMESTAMP WITH TIME ZONE NOT NULL,
  is_auto_generated BOOLEAN DEFAULT TRUE,
  is_visible BOOLEAN DEFAULT TRUE, -- user can hide events
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE INDEX idx_timeline_pet_date ON timeline_events(pet_id, event_date DESC);
CREATE INDEX idx_timeline_type ON timeline_events(pet_id, event_type);
CREATE INDEX idx_timeline_visible ON timeline_events(pet_id, is_visible,
event_date DESC);
```

```
CREATE TABLE pet_memorial (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  passed_date DATE NOT NULL,
  activated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  memorial_pdf_url VARCHAR(500), -- generated PDF location
  UNIQUE(pet_id)
);
```

5.7.7 API Endpoints

Method	Endpoint	Description
GET	/api/timeline/{pet_id}?page=1&limit=50&filter=all	Get timeline events (paginated, filtered)
POST	/api/timeline/{pet_id}	Create manual timeline entry

PUT	/api/timeline/{id}/visibility	Show/hide a timeline event
DELETE	/api/timeline/{id}	Delete manual entry (auto entries cannot be deleted)
POST	/api/timeline/{pet_id}/memorial	Activate Memorial Mode
GET	/api/timeline/{pet_id}/memorial/export	Generate Memorial PDF (Premium)
GET	/api/timeline/{pet_id}/stats	Get timeline statistics (total events, photos, milestones)

END OF DOCUMENT 2: CORE FEATURES

This document covers 7 core features with complete specifications:

5.1 Care Garden Visualization — 6 species icons, 3 states, Full Bloom, decor unlocks

5.2 Task Streak Badges — 6 tiers, skip system, celebrations, share images

5.3 Health Tracking — Weight, vet visits, medications, medical disclaimers

5.4 Custom Trackers — 10 templates + custom creation, limits

5.5 Photo Gallery — Processing pipeline, 3 views, timeline integration

5.6 Interactive Avatar — 4 moods, 16 Lottie files, calculation algorithm

5.7 Pet Legacy Timeline — Auto-capture, Memorial Mode, PDF export

Continue to Document 3 (Social, Planner & System Features) for Care Circles, Daily Planner, Notifications, Pet Selector, Admin Panel, and Invisible AI.

Continue to Document 4 (Party Kits) for the complete 40-page Party Kit specification.

POSHPET

Phase 1 Technical Documentation

Document 3 of 5: Social, Planner & System Features

Care Circles | Daily Planner | Notifications | Pet Selector
Customization | Admin Panel | Invisible AI | Exclusions

Version 3.0 | February 2026

5.8 CARE CIRCLES — PRIVATE GROUPS

Care Circles are private, invitation-only groups where family members and trusted friends share pet care updates, photos, and contribute to Party Kit celebrations. Care Circles provide the emotional benefits of social sharing without the toxicity of public pet social networks.

5.8.1 Circle Specifications

Members: Minimum 2, Maximum 20 per circle

Creation: Premium users only can create circles. Free users can join circles.

Circles per user: Create up to 5 circles (Premium). Join unlimited circles.

Naming: Circle name required (50 characters max). Optional circle description (200 characters max). Optional circle photo (group avatar).

Privacy: All circles are private. No discovery, no search, no public listing. Members see only circles they belong to.

5.8.2 Invitation System

Invite Methods:

Share Link: Unique URL that expires after 7 days. Link opens PoshPet with join prompt. If user doesn't have PoshPet, link goes to App Store / Play Store.

In-App Invite: Search by email (only matches existing PoshPet users). Selected user receives in-app notification to accept/decline.

QR Code: Scannable QR code for in-person invitations. Expires after 24 hours.

Roles:

Owner: Created the circle. Can invite, remove members, edit circle info, delete circle, manage moderation settings. 1 per circle.

Admin: Promoted by owner. Can invite members, remove non-admin members, moderate posts. Up to 3 per circle.

Member: Can post, react, comment, contribute to Party Kits. Cannot invite or remove others.

5.8.3 Shared Content Types

Circle members can share the following content within a circle:

Photos: Share from gallery or take new. Caption optional. Visible to all circle members.

Milestones: Streak badges, Full Bloom achievements auto-shared if user enables 'Share milestones to circles' in settings.

Updates: Text posts up to 500 characters. Can include one photo attachment.

Care check-ins: 'Today was a [great/good/tough] day for [Pet Name]' quick status with optional note. Displayed as compact card with emoji indicator.

Timeline highlights: User selects specific timeline events to share (not automatic). Shared as read-only event card.

5.8.4 Interaction Features

Reactions

6 reaction types: ❤️ Love (heart), 🐾 Paw (cute), ⭐ Star (amazing), 😂 Laugh, 🥺 Aww (sympathy), 🎉 Celebrate. Tap to add reaction, tap again to remove. Reaction counts visible below post. Tap count to see who reacted.

Comments

Max length: 300 characters per comment

Threading: Single-level replies only (no nested threads to keep simple)

Editing: Author can edit within 15 minutes of posting

Deletion: Author can delete own comments anytime. Admin/Owner can delete any comment.

Circle Feed

Reverse chronological feed of all shared content. Pull-to-refresh. Infinite scroll with 20 posts per page. Unread indicator badge on circle icon in navigation.

5.8.5 Party Kit Contribution Flow

Care Circles integrate directly with Party Kits. When a circle member is completing a Party Kit that includes a 'Circle Contribution' step, they can invite circle members to contribute. This is how families create shared celebration memories.

5-Step Contribution Process:

Step 1 — Request: Kit creator taps 'Invite Circle' on the contribution step. Selects which circle(s) to invite. Sets deadline (1-14 days).

Step 2 — Notification: All circle members receive push notification: '[Name] is celebrating [Pet]'s birthday! Add your message.' In-app card appears in circle feed.

Step 3 — Contribute: Each member can submit: text message (500 chars max), photo (from gallery or camera), voice note (30 seconds max). One contribution per member per kit. Members can edit/replace their contribution until the deadline.

Step 4 — Assembly: After deadline passes (or creator manually closes contributions), all submissions are assembled into the Living Memory Page. Creator can preview and reorder contributions before finalizing.

Step 5 — Celebration: Completed Memory Page with all contributions visible in the kit completion experience. Contributors get notification: 'The Memory Page for [Pet]'s birthday is ready!'

5.8.6 Moderation System

Admin Controls:

Approve posts: Optional setting: require admin approval before posts appear (off by default)

Remove content: Owner/Admin can remove any post, photo, or comment

Remove members: Owner can remove anyone. Admins can remove non-admin members.

Mute members: Temporarily prevent a member from posting (24hr, 7 days, 30 days)

Keyword filtering: Optional custom blocked words list. Posts containing blocked words are held for review.

Reporting:

Any member can report a post, comment, or member. Reports go to circle Owner/Admins first. If unresolved or if reporting owner, reports escalate to PoshPet admin panel. Report categories: Inappropriate content, Spam, Harassment, Other.

5.8.7 Database Schema

```
CREATE TABLE care_circles (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  owner_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  name VARCHAR(50) NOT NULL,
  description VARCHAR(200),
  photo_url VARCHAR(500),
  member_count INTEGER DEFAULT 1,
  require_post_approval BOOLEAN DEFAULT FALSE,
  blocked_words TEXT[],
  invite_link VARCHAR(100) UNIQUE,
  invite_link_expires_at TIMESTAMP WITH TIME ZONE,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE TABLE circle_members (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  circle_id UUID NOT NULL REFERENCES care_circles(id) ON DELETE CASCADE,
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  role VARCHAR(20) NOT NULL DEFAULT 'member', -- 'owner', 'admin', 'member'
  joined_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  muted_until TIMESTAMP WITH TIME ZONE,
  UNIQUE(circle_id, user_id)
);

CREATE TABLE circle_posts (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  circle_id UUID NOT NULL REFERENCES care_circles(id) ON DELETE CASCADE,
  author_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  post_type VARCHAR(30) NOT NULL, -- 'photo', 'milestone', 'update',
  'checkin', 'timeline_highlight'
  content TEXT,
  media_url VARCHAR(500),
  metadata JSONB,
  is_approved BOOLEAN DEFAULT TRUE,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  edited_at TIMESTAMP WITH TIME ZONE
```

```

);

CREATE TABLE circle_comments (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  post_id UUID NOT NULL REFERENCES circle_posts(id) ON DELETE CASCADE,
  author_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  parent_comment_id UUID REFERENCES circle_comments(id) ON DELETE CASCADE,
  content VARCHAR(300) NOT NULL,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  edited_at TIMESTAMP WITH TIME ZONE
);

CREATE TABLE circle_reactions (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  post_id UUID NOT NULL REFERENCES circle_posts(id) ON DELETE CASCADE,
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  reaction_type VARCHAR(20) NOT NULL, -- 'love', 'paw', 'star', 'laugh',
  'aww', 'celebrate'
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  UNIQUE(post_id, user_id, reaction_type)
);

CREATE TABLE circle_reports (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  circle_id UUID NOT NULL REFERENCES care_circles(id) ON DELETE CASCADE,
  reporter_id UUID NOT NULL REFERENCES users(id),
  reported_post_id UUID REFERENCES circle_posts(id),
  reported_user_id UUID REFERENCES users(id),
  reason VARCHAR(30) NOT NULL,
  details VARCHAR(500),
  status VARCHAR(20) DEFAULT 'pending', -- 'pending', 'resolved', 'escalated'
  resolved_by UUID REFERENCES users(id),
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

```

5.8.8 API Endpoints

Method	Endpoint	Description
POST	/api/circles	Create new circle (Premium)
GET	/api/circles	Get all circles user belongs to
GET	/api/circles/{id}	Get circle details + member list
PUT	/api/circles/{id}	Update circle name, description, photo, settings
DELETE	/api/circles/{id}	Delete circle (Owner only)

POST	/api/circles/{id}/invite	Generate invite link or send direct invite
POST	/api/circles/{id}/join	Join circle via invite link
DELETE	/api/circles/{id}/members/{user_id}	Remove member
PUT	/api/circles/{id}/members/{user_id}/role	Change member role
GET	/api/circles/{id}/feed?page=1	Get circle feed (paginated)
POST	/api/circles/{id}/posts	Create new post
DELETE	/api/circles/posts/{id}	Delete post
POST	/api/circles/posts/{id}/reactions	Add/remove reaction
POST	/api/circles/posts/{id}/comments	Add comment
POST	/api/circles/{id}/report	Report content or member

5.9 ANIMATED TRANSITIONS

All transitions follow PoshPet's luxury design philosophy: silk-smooth, purposeful, and never jarring. Every animation has a functional purpose (orientation, feedback, or delight). Performance target: 60fps on all devices.

5.9.1 Navigation Transitions

Transition	Animation	Duration	Easing
Screen push (forward)	New screen slides in from right, current slides left. Both at 50% opacity during motion.	400ms	cubic-bezier(0.4, 0, 0.2, 1)
Screen pop (back)	Current screen slides right, previous slides in from left.	350ms	cubic-bezier(0.4, 0, 0.2, 1)
Modal open	Slides up from bottom with backdrop fade (0 to 40% black). Content fades in at 200ms delay.	500ms	Spring (damping: 0.8)
Modal close	Slides down, backdrop fades out.	400ms	cubic-bezier(0.4, 0, 1, 1)
Tab switch	Crossfade between tab contents. No sliding.	300ms	ease-in-out
Bottom sheet	Slides up from bottom, content can be dragged to dismiss.	400ms	Spring physics

5.9.2 Micro-Interactions

Element	Animation	Duration
Button press	Scale to 0.96, subtle shadow reduction	200ms
Button release	Spring back to 1.0	300ms (spring)
Task complete (long-press)	Radial teal fill from press point, checkmark draws in, card slides right off screen	600ms total
Toggle switch	Thumb slides with slight bounce, background color crossfades	300ms
Pull-to-refresh	Custom Lottie animation: small pet paw pulling down, sparkle on release	Variable
Skeleton loading	Shimmer gradient sweep left-to-right on placeholder shapes	1500ms loop
Toast notification	Slides down from top, auto-dismisses after 3 seconds, swipe up to dismiss early	300ms in, 200ms out

5.9.3 Celebration Animations

Event	Animation Description	Duration
Full Bloom	All garden icons pulse, rose gold particles rise, golden glow, 'Full Bloom!' text	3 seconds
Badge unlock	Screen dims, badge enters from bottom, particles burst, name + count display	2.5 seconds
Party Kit completion	Cinematic: pet animation, Memory Page reveal, emotional copy, confetti	8-10 seconds
Time Capsule seal	Envelope folds, wax stamp drops, seal hardens with shine	2 seconds
Time Capsule unseal	Wax melts, envelope unfolds, golden light beams out, content reveals	3 seconds

5.9.4 Implementation & Accessibility

Mobile: React Native Reanimated 3.x for gesture-driven and layout animations. Lottie React Native for complex pre-built animations.

Web: Framer Motion for layout and transition animations. Lottie Web for complex pre-built animations.

Reduced motion: ALL animations respect the prefers-reduced-motion media query. When enabled: transitions become instant cuts (0ms), celebrations show static result without animation, avatar shows static illustration, garden icons switch state instantly without fill animation. Functionality is never reduced—only visual motion is removed.

Performance: All animations use GPU-accelerated properties only (transform, opacity). Avoid animating layout properties (width, height, top, left). Pre-cache Lottie files on app launch for instant playback.

5.10 DAILY PLANNER & CALENDAR VIEW

The Daily Planner is the central hub of PoshPet. Users open the app to this screen every day. It must be fast (under 2 seconds to fully render), beautiful, and satisfying to interact with. The planner has two views: Today (daily task list) and Calendar (monthly overview).

5.10.1 Today View Layout

Top-to-bottom screen structure on mobile:

- 1. Header Bar (56px height):** Pet name (left, Canela serif, 20px). Pet selector dropdown arrow. Settings gear icon (right). Background: cream (#F5F5DC).
- 2. Pet Avatar (200×200px):** Centered horizontally. Animated mood state (see 5.6). Tap avatar for quick pet profile view.
- 3. Care Garden Strip (80px height):** Species-specific icons showing today's progress (see 5.1). Full width with 20px side padding.
- 4. Date & Progress (40px):** Today's date in Canela serif (16px). Task counter: '4 of 6 complete' in body font (14px, gray). Horizontally centered.
- 5. Task List (remaining height):** Scrollable list of today's task cards. Each card 72px height. 16px padding from screen edges. 8px gap between cards. Pull-to-refresh enabled.
- 6. Bottom Tab Bar (80px):** 4 tabs: Today (house icon), Calendar (grid icon), Health (heart icon), Timeline (clock icon). Active tab: teal icon + label. Inactive: gray icon, no label.

5.10.2 Task Card Design

Card Dimensions:

Height: 72px (fixed for visual consistency)

Width: Full screen width minus 32px (16px margin each side)

Background: White (#FFFFFF)

Border radius: 12px

Shadow: 0 2px 8px rgba(0,0,0,0.08)

Card Content Layout:

Left (16px from left edge): Task icon (32×32px), species-appropriate or custom icon. Teal when pending, gray when complete.

Center: Task name (16px, Medium weight, charcoal #333333). Scheduled time below (14px, Regular, gray #666666). If task has streak: streak count shown inline ('42-day streak').

Right (16px from right edge): Streak badge icon (24×24px) if applicable. Completion indicator: empty circle (pending) or filled teal circle with white checkmark (complete).

Completed Card State:

Background shifts to faint teal tint (rgba(0,139,139,0.05)). Task name gets subtle strikethrough (1px, gray). Card moves to bottom of list with smooth 300ms slide animation. Overall opacity: 80%.

5.10.3 Task Completion Methods

Method 1: Long Press (Primary, Mobile)

Action: Press and hold anywhere on task card for 1.5 seconds.

Visual feedback: Radial teal fill spreads from press point during hold. At 0.75 seconds (halfway), subtle vibration. At 1.5 seconds, full teal wash, haptic bump, checkmark draws in.

Post-completion: Card slides right off screen (400ms). Corresponding garden icon begins fill animation simultaneously. Avatar mood recalculates.

Method 2: Swipe Right (Secondary, Mobile)

Action: Swipe task card to the right.

Visual feedback: Teal checkmark reveals behind card as it slides. Release past 40% threshold to complete. Below threshold, card springs back.

Method 3: Tap Checkbox (Web/Accessibility)

Action: Click/tap the circular completion indicator on right side of card.

Visual feedback: Circle fills with teal, checkmark draws in (300ms). Card fades to completed state.

5.10.4 Calendar View

Monthly Grid:

Standard 7-column calendar grid. Header shows month name (Canela serif, 24px) with left/right arrows for navigation. Day cells: 48×48px minimum on mobile. Current day: teal circle behind date number. Days with Full Bloom: gold border ring around the date cell. Days with partial completion: small teal dot below date number. Future days: lighter text (#999999). Past days with no activity: normal text.

Day Detail:

Tapping any day opens that day's task list as a bottom sheet. Shows completed vs incomplete tasks for that date. Historical days are read-only (cannot complete past tasks). Future days show scheduled tasks.

Streak Visualization:

If user has active streaks, consecutive completed days show a subtle teal underline connecting them horizontally across the calendar row.

5.10.5 Default Tasks by Species

When user adds a new pet, default daily tasks are created based on species. Users can modify, add, or remove any default task.

Species	Default Tasks
Dogs	Morning Walk, Breakfast, Evening Walk, Dinner, Fresh Water, Brush Coat (weekly)
Cats	Breakfast, Dinner, Fresh Water, Litter Box, Playtime, Brush Coat (weekly)
Fish	Morning Feeding, Check Water Temp, Check Filter, Water Change (weekly)

Birds	Morning Feeding, Fresh Water, Cage Clean Spot Check, Enrichment/Out-of-Cage Time
Rabbits	Morning Hay, Pellet Feeding, Fresh Water, Litter Clean, Exercise Time, Nail Check (monthly)
Guinea Pigs	Hay Refill, Veggie Feeding, Fresh Water, Spot Clean Cage, Floor Time
Hamsters	Evening Feeding, Fresh Water, Wheel Check, Spot Clean, Handling Time
Reptiles	Feeding (varies by species), Check Temp/Humidity, Misting (if tropical), Spot Clean, UV Light Check

All default tasks come with suggested times based on species needs. Users are prompted to review and customize defaults during pet onboarding.

5.10.6 Database Schema

```
CREATE TABLE task_templates (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  name VARCHAR(100) NOT NULL,
  icon VARCHAR(50) DEFAULT 'paw',
  scheduled_time TIME,
  frequency VARCHAR(20) NOT NULL DEFAULT 'daily', -- 'daily', 'weekly',
'monthly', etc.
  frequency_days INTEGER[], -- [1,3,5] for Mon/Wed/Fri
  is_default BOOLEAN DEFAULT FALSE,
  is_active BOOLEAN DEFAULT TRUE,
  display_order INTEGER DEFAULT 0,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);

CREATE TABLE task_instances (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  task_template_id UUID NOT NULL REFERENCES task_templates(id) ON DELETE
CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  scheduled_date DATE NOT NULL,
  scheduled_time TIME,
  status VARCHAR(20) DEFAULT 'pending', -- 'pending', 'completed', 'skipped'
  completed_at TIMESTAMP WITH TIME ZONE,
  skipped_reason VARCHAR(50),
  notes VARCHAR(200),
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  UNIQUE(task_template_id, scheduled_date)
);

CREATE INDEX idx_tasks_pet_date ON task_instances(pet_id, scheduled_date);
CREATE INDEX idx_tasks_status ON task_instances(pet_id, scheduled_date,
status);
```

5.10.7 API Endpoints

Method	Endpoint	Description
GET	/api/planner/{pet_id}/today	Get today's tasks with completion status
GET	/api/planner/{pet_id}/date/{date}	Get tasks for a specific date
GET	/api/planner/{pet_id}/calendar/{year}/{month}	Get monthly calendar summary (bloom days, completion dots)
POST	/api/planner/{pet_id}/tasks	Create new task template
PUT	/api/planner/tasks/{id}	Update task template (name, time, frequency)
DELETE	/api/planner/tasks/{id}	Delete task template
POST	/api/planner/tasks/{instance_id}/complete	Mark task instance as completed
POST	/api/planner/tasks/{instance_id}/skip	Mark task instance as skipped
PUT	/api/planner/{pet_id}/reorder	Reorder task display order

5.11 SMART NOTIFICATION SYSTEM

Notifications must feel helpful, not nagging. Every notification has purpose and respects the user's time. The system learns patterns and adjusts delivery for maximum engagement with minimum annoyance.

5.11.1 Notification Types

Type	Trigger	Example Copy	Priority
Task Reminder	Task scheduled time arrives	'Time for [Pet]'s evening walk 🐾'	Normal
Streak Protection	End of day, task incomplete, active streak at risk	'Don't lose your 42-day walk streak! [Pet] is waiting.'	High
Full Bloom Nudge	1 task remaining for Full Bloom, evening	'One task left for Full Bloom! [Pet]'s garden is almost complete ✨'	Normal
Party Kit Step	Next kit step ready based on pacing	'Time for the next step in [Pet]'s birthday celebration!'	Normal
Time Capsule Delivery	1 year since capsule sealed	'A message from the past is waiting for you... 💌'	High
Care Circle Activity	New post, comment, or reaction in circle	'[Name] shared a photo of [Pet] in [Circle Name]'	Low
Medication Reminder	Medication dose time	'Time for [Pet]'s [Medication Name]'	High
Vet Follow-up	Follow-up date arrives for vet visit	'[Pet]'s follow-up at [Clinic] is scheduled for today'	Normal
Subscription	Trial ending, payment failed, renewal	'Your PoshPet Society trial ends in 3 days'	Normal
Welcome Series	Days 1, 3, 7 after signup	'[Pet] is settling in! Have you tried the Care Garden?'	Low

5.11.2 Quiet Hours

Default: 10:00 PM – 8:00 AM (user's local timezone)

Customizable: User can adjust start and end times in Settings

Behavior: All notifications held during quiet hours, delivered at quiet hours end

Override: Only Time Capsule delivery and medication reminders can override quiet hours (user opts in separately)

5.11.3 Frequency Limits

Maximum per day: 5 notifications (excludes medication reminders)

Minimum gap: 30 minutes between non-medication notifications

Cooldown: If user dismisses 3 notifications without opening app, reduce frequency for 48 hours

Priority ordering: When limit reached, highest-priority notifications sent first. Lower-priority notifications dropped, not queued.

5.11.4 Streak Protection Logic

The most critical notification type. Prevents accidental streak loss.

First warning: 6:00 PM local time if task incomplete and streak active

Second warning: 8:00 PM if still incomplete

Final warning: 9:30 PM (30 min before quiet hours) with urgent copy: 'Last chance to save your [X]-day streak!'

No notification if: User has already completed the task, streak is 0 (nothing to protect), user has disabled streak notifications

5.11.5 Notification Intelligence (Invisible AI)

Over time, the system learns user patterns:

Timing optimization: If user consistently completes walks at 7 AM, reminder shifts from default scheduled time to 6:55 AM.

Delivery channel: If user ignores push notifications but opens app organically, reduce push frequency and rely on in-app badges.

Day-of-week patterns: If user skips tasks on Sundays, reduce Sunday notification frequency.

Engagement scoring: Track notification open rates per type. Reduce low-engagement types, maintain high-engagement types.

5.11.6 Database Schema

```
CREATE TABLE notification_preferences (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  quiet_hours_start TIME DEFAULT '22:00',
  quiet_hours_end TIME DEFAULT '08:00',
  task_reminders_enabled BOOLEAN DEFAULT TRUE,
  streak_protection_enabled BOOLEAN DEFAULT TRUE,
  circle_activity_enabled BOOLEAN DEFAULT TRUE,
  party_kit_enabled BOOLEAN DEFAULT TRUE,
  medication_override_quiet BOOLEAN DEFAULT FALSE,
  capsule_override_quiet BOOLEAN DEFAULT TRUE,
  max_daily_notifications INTEGER DEFAULT 5,
  UNIQUE(user_id)
);
```

```
CREATE TABLE notification_logs (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
```

```

notification_type VARCHAR(50) NOT NULL,
title VARCHAR(200),
body VARCHAR(500),
priority VARCHAR(10) DEFAULT 'normal',
sent_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
opened_at TIMESTAMP WITH TIME ZONE,
dismissed_at TIMESTAMP WITH TIME ZONE,
delivery_channel VARCHAR(20) DEFAULT 'push' -- 'push', 'in_app', 'email'
);
CREATE INDEX idx_notif_user_date ON notification_logs(user_id, sent_at DESC);

```

5.11.7 API Endpoints

Method	Endpoint	Description
GET	/api/notifications/preferences	Get user notification settings
PUT	/api/notifications/preferences	Update notification settings
GET	/api/notifications/history?page=1	Get notification history (paginated)
POST	/api/notifications/register-device	Register device token for push notifications
PUT	/api/notifications/{id}/read	Mark notification as read
POST	/api/notifications/test	Send test notification (debug/admin)

5.12 PET SELECTOR / MULTI-PET SUPPORT

Multi-pet support is a primary conversion driver. Free users are limited to 1 pet. Anyone with 2+ pets MUST upgrade to Premium.

5.12.1 Pet Limits

Free tier: 1 pet maximum

Premium tier: Unlimited pets

Upgrade prompt: When free user taps 'Add Pet,' show upgrade modal: 'Add unlimited pets with PoshPet Society. \$14.99/month.' Include 7-day free trial option.

5.12.2 Pet Selector UI

Location:

Top-left of header bar on all main screens. Current pet's name displayed with dropdown arrow icon.

Tap Behavior:

Tapping opens dropdown menu below header. Each pet listed with: circular avatar thumbnail (40×40px), pet name, species icon, current mood indicator (small colored dot: green=happy, yellow=waiting, red=sad, blue=sleeping). Active pet highlighted with teal background.

Dropdown height: auto-sized to content, max 5 pets visible before scrolling. Animation: slides down over 300ms with spring easing.

'All Pets' Combined View (Premium Only)

Premium users see 'All Pets' option at top of dropdown. Combined view shows:

Daily Planner: Tasks grouped by pet with pet name headers. Each section has its own mini garden strip.

Calendar: Color-coded dots per pet on calendar days.

Timeline: Interleaved timeline from all pets with pet avatar badge on each event.

Combined view does not show avatar mood (only single-pet view shows avatar).

5.12.3 Adding a New Pet

Onboarding Flow (4 screens):

Screen 1 — Pet Name: Text input, required, 30 characters max. Large friendly heading: 'What's your pet's name?'

Screen 2 — Species Selection: Grid of 14 species with icons. Each species tile: 80×80px icon with name below. Tap to select (teal border highlight). If animated species selected: preview of happy avatar animation.

Screen 3 — Details: Breed: text input with breed suggestions from database (optional). Birthday/adoption date: date picker (optional but encouraged for Party Kits). Gender: Male, Female, Unknown. Size: Small, Medium, Large (dogs only).

Screen 4 — Photo: Camera or gallery upload for pet profile photo. Crop to circle (200×200px). Skip option available. Preview with 'Looking great!' confirmation text.

After completion: default tasks created based on species. User prompted to review and customize. Brief tutorial overlay highlighting Care Garden and avatar.

5.12.4 Database Schema

```
CREATE TABLE pets (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  name VARCHAR(30) NOT NULL,
  species VARCHAR(30) NOT NULL,
  breed VARCHAR(100),
  birthday DATE,
  adoption_date DATE,
  gender VARCHAR(10),
  size VARCHAR(10),
  photo_url VARCHAR(500),
  photo_thumbnail_url VARCHAR(500),
  is_active BOOLEAN DEFAULT TRUE,
  is_memorial BOOLEAN DEFAULT FALSE,
  display_order INTEGER DEFAULT 0,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  updated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);
CREATE INDEX idx_pets_user ON pets(user_id, display_order);
```

5.12.5 API Endpoints

Method	Endpoint	Description
GET	/api/pets	Get all pets for current user
POST	/api/pets	Create new pet (enforces tier limit)
GET	/api/pets/{id}	Get pet profile details
PUT	/api/pets/{id}	Update pet info (name, breed, photo, etc.)
DELETE	/api/pets/{id}	Soft delete pet (marks inactive, data preserved 90 days)
PUT	/api/pets/reorder	Update display order for pet selector
GET	/api/pets/combined/today	Get combined daily view for all pets (Premium)

5.13 PLANNER CUSTOMIZATION SETTINGS

Settings that let users personalize their planner experience without affecting core functionality.

5.13.1 Module Visibility (Show/Hide)

Users can toggle visibility of non-essential modules:

Module	Default	Hideable?	Notes
Care Garden strip	Visible	Yes	Hides garden, tasks still tracked
Avatar	Visible	Yes	Hides avatar area, frees vertical space
Streak badges on task cards	Visible	Yes	Hides badge icons, streaks still tracked in background
Health tab	Visible	Yes	Hides from bottom nav
Timeline tab	Visible	No	Core feature, always accessible
Task time display	Visible	Yes	Hides scheduled times on task cards

5.13.2 Planner Themes (Premium Only)

Theme Name	Background	Accent Color	Card Style	Mood
Classic (default)	Cream (#F5F5DC)	Teal (#008B8B)	White cards, subtle shadow	Warm, natural
Midnight	Dark navy (#1A1B2E)	Gold (#FFD700)	Dark gray cards (#2A2B3E)	Sophisticated evening
Botanical	Soft sage (#E8EDE4)	Forest green (#2D5F2D)	White with green accents	Nature-inspired calm
Blush	Pale pink (#FFF0F5)	Rose (#C77D8A)	White with pink accents	Soft, feminine warmth

Theme changes apply to: background color, accent colors on buttons and active elements, card backgrounds, text colors (adjusted for contrast). Theme does NOT change: Lottie animations, garden icons, avatar designs, celebration effects.

5.13.3 Task Completion Style

Option	Behavior	Visual
Full (default)	Long-press fill + card slide + haptic + sound	Maximum celebration
Quick	Single tap checkbox, instant complete	Checkmark only, no animation
Minimal	Swipe right, card fades to complete state	Subtle, stays in place

5.13.4 Celebration Intensity

Full (default): All celebrations with particles, sounds, and haptics

Subtle: Reduced particles (50%), no sound, gentle haptics

None: No celebrations. Tasks silently complete. Badges unlock without fanfare.

5.13.5 Database Schema

```
CREATE TABLE planner_preferences (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  show_garden BOOLEAN DEFAULT TRUE,
  show_avatar BOOLEAN DEFAULT TRUE,
  show_streak_badges BOOLEAN DEFAULT TRUE,
  show_health_tab BOOLEAN DEFAULT TRUE,
  show_task_times BOOLEAN DEFAULT TRUE,
  theme VARCHAR(20) DEFAULT 'classic',
  completion_style VARCHAR(20) DEFAULT 'full',
  celebration_intensity VARCHAR(20) DEFAULT 'full',
  weight_unit VARCHAR(3) DEFAULT 'lbs',
  timezone VARCHAR(50),
  UNIQUE(user_id)
);
```

5.15 ADMIN PANEL

A web-based administration interface for the solo founder to manage users, subscriptions, content, Party Kits, and view basic analytics. Accessible via separate admin URL with additional authentication.

5.15.1 Authentication & Access

URL: admin.poshpet.app (or /admin route on main web app)

Access: Superadmin role only (hardcoded admin email in environment variable)

Additional auth: Requires 2FA (authenticator app) on top of standard login

Session: 4-hour session timeout, re-authentication required

5.15.2 User Management

User List:

Searchable table with columns: Name, Email, Plan (Free/Premium), Joined Date, Last Active, Pet Count, Status (Active/Suspended). Pagination: 50 users per page. Filters: Plan type, join date range, activity status.

User Detail View:

Full user profile with: all pets, subscription details (Stripe customer ID link), activity metrics (DAU, tasks completed, photos uploaded), Care Circles membership, Party Kits in progress/completed, flag for support or investigation.

Admin Actions:

Suspend user: Temporarily disable account with reason. User sees 'Account suspended, contact support.'

Delete user: GDPR compliance deletion. Removes all personal data. Requires typing 'DELETE' to confirm.

Grant Premium: Manually give Premium access (for support issues, partnerships, testing)

Send message: System message to user's notification inbox

5.15.3 Subscription Management

Integration with Stripe Dashboard for detailed billing. Admin panel shows:

MRR: Monthly Recurring Revenue (calculated from active subscriptions)

Subscriber count: Total active Premium subscribers with month-over-month trend

Churn rate: Percentage of subscribers who cancelled in last 30 days

Trial conversions: Percentage of free trial users who became paying subscribers

Failed payments: List of failed payments with retry status. Quick action to extend grace period.

5.15.4 Content Oversight

Moderation Queue:

All reported content from Care Circles appears here. Each report shows: reporter name, reported content/user, report reason, circle name, timestamp. Admin actions: Remove content, Warn user, Suspend user, Dismiss report (false flag).

Photo Review:

Random sample of recently uploaded photos for spot-check moderation. Flag for review if concerning. Automated NSFW detection recommended (AWS Rekognition or similar) to pre-filter.

5.15.5 Party Kit Management

View all kits: List of all kit templates with status (active/draft/disabled)

Edit kit content: Modify step text, reorder steps, update emotional copy, adjust timing

Toggle kit availability: Enable/disable specific kits without deploying code

Preview kit: Step-through preview of entire kit experience as user would see it

Usage statistics: How many users started each kit, completion rate, average time to complete

5.15.6 Analytics Dashboard

Basic metrics displayed on admin dashboard home page. Not a full analytics suite—detailed analytics come from Mixpanel/Amplitude integration.

DAU / WAU / MAU: Daily, weekly, monthly active users with sparkline trend

Task completion rate: Average daily task completion percentage across all users

Full Bloom rate: Percentage of active users achieving Full Bloom daily

Conversion rate: Free to Premium conversion (7-day, 30-day, 90-day windows)

Retention: Day 1, Day 7, Day 30 retention rates

Feature usage: Top 10 most-used features ranked by daily interaction count

Kit engagement: Party Kit start rate, completion rate, Time Capsule seal rate

5.15.7 What Is NOT in Admin Panel

The following are handled by external services, not the admin panel:

Detailed billing: Stripe Dashboard (invoices, refunds, disputes)

Error tracking: Sentry Dashboard (crash reports, error rates)

Deep analytics: Mixpanel or Amplitude (funnels, cohorts, A/B tests)

Infrastructure: Railway/Render/Vercel dashboards (deploys, logs, scaling)

Email campaigns: Mailchimp or similar (welcome emails, re-engagement)

5.16 INVISIBLE AI

Core principle: The user NEVER knows AI exists in PoshPet. There is no 'AI' label, no chatbot, no 'powered by AI' badge, no AI-generated text visible to users. The app simply feels smarter over time. Users say 'PoshPet just gets me' without knowing why.

5.16.1 Smarter Planner

Reminder Timing Optimization:

The system tracks when users typically complete each task (e.g., walks at 7:15 AM, feeding at 6:00 PM). After 14 days of data, reminder times auto-adjust to 5 minutes before the user's typical completion time. If user's pattern shifts (e.g., starts walking at 8 AM instead of 7 AM), system adjusts within 3-5 days of new pattern.

Task Spacing:

If user has 6 tasks and tends to complete them in 3 bursts (morning, afternoon, evening), the planner subtly groups task reminders into these natural windows rather than spreading them evenly.

Weekend/Weekday Patterns:

System detects different routines for weekdays vs weekends. Reminder timing, notification frequency, and task ordering can differ by day type.

5.16.2 Kit Intelligence (Premium)

Pacing Adjustment:

If a user engages with Party Kit steps quickly (same day), the system can accelerate step delivery slightly. If a user takes 3+ days between steps, the system extends pacing and sends gentler nudges. The algorithm prevents kit completion from feeling rushed or abandoned.

Engagement Adaptation:

If user responds to text prompts with long, detailed answers, subsequent text steps can indicate '(Take your time with this one)' as hint text. If user responds briefly, the system doesn't judge—it simply keeps the experience flowing.

5.16.3 Notification Intelligence

Smart Bundling:

If 3 notifications would fire within 30 minutes, bundle into one: 'You have 3 tasks due this morning for [Pet]' instead of 3 separate pings.

Suppression:

If user opens app organically every morning at 7 AM, suppress the 7 AM task reminder (they're already in the app). Resume reminders if organic pattern breaks for 3+ days.

Escalation:

For streak protection: first reminder is casual. Second is slightly more urgent. Third uses pet's name emotionally. Copy escalation is pre-written (not generated), but delivery timing is intelligent.

5.16.4 Technical Approach

Phase 1 implementation: 80% rules-based, 20% simple ML

Rules engine: IF/THEN logic for notification timing, streak protection, kit pacing. Configurable in admin panel without code deploys.

Simple ML: Rolling averages of completion times. Standard deviation to detect pattern changes. No deep learning, no GPT, no external AI services.

Data scope: All learning is LOCAL to each user. No cross-user data sharing. No collaborative filtering. Each user's patterns are independent.

Privacy: All behavior data stored in user's own database records. Deleted when user deletes account. Never used for advertising or third-party purposes.

5.16.5 What Invisible AI Is NOT

NOT a chatbot: No conversational AI interface anywhere in the app

NOT generative: No AI-written text, captions, or suggestions visible to users

NOT diagnostic: No health predictions, symptom analysis, or medical AI

NOT recommendation engine: No 'pets like yours also...' features

NOT surveillance: No tracking beyond app usage patterns for the features described above

5.17 PHASE 1 EXCLUSIONS

This section explicitly states what PoshPet Phase 1 does NOT include. This prevents scope creep during development and sets clear expectations.

5.17.1 Features Reserved for Phase 2

Service Provider Marketplace: No booking, scheduling, or payments for vets, groomers, walkers, trainers

GPS Tracking: No real-time location tracking for walks or pet sitters

Provider Reviews: No rating or review system for service providers

International: English only, US-centric defaults. International expansion in Phase 2.

5.17.2 Features Reserved for Phase 3

Product Marketplace: No e-commerce, product listings, or affiliate links

Subscription Boxes: No curated product boxes or physical goods

5.17.3 Features That Will NEVER Be Built

Medical Diagnosis: PoshPet will never diagnose health conditions, interpret symptoms, or recommend treatments. Health tracking is observation-only logging for personal records.

AI Health Predictions: No predictive health alerts, disease risk scores, or health trend analysis. The liability exposure and potential for harm make this permanently excluded.

Connected Devices: No integration with smart collars, GPS trackers, health monitors, or IoT devices. These require hardware partnerships and ongoing maintenance that are out of scope.

Public Social Features: No public profiles, public feeds, follower counts, user discovery, pet-to-pet matching, or influencer programs. PoshPet is a private care planner, not a social network.

Enterprise Features: No multi-user business accounts, veterinary clinic integrations, kennel management systems, white-label solutions, or third-party API access.

User-Generated Content Marketplace: No ability for users to sell templates, trackers, or content to other users.

END OF DOCUMENT 3: SOCIAL, PLANNER & SYSTEM FEATURES

This document covers 8 features and the exclusions list:

5.8 Care Circles — Private groups, invitations, roles, contributions, moderation

5.9 Animated Transitions — Navigation, micro-interactions, celebration timing specs

5.10 Daily Planner & Calendar — Today view layout, task cards, completion methods, default tasks by species

5.11 Smart Notifications — 10 types, quiet hours, frequency limits, streak protection, intelligence

5.12 Pet Selector / Multi-Pet — Tier limits, combined view, onboarding flow

5.13 Planner Customization — Module visibility, 4 themes, completion styles, celebration intensity

5.15 Admin Panel — User management, subscriptions, moderation, kit management, analytics

5.16 Invisible AI — Smart timing, kit pacing, notification intelligence, privacy

5.17 Exclusions — Phase 2, Phase 3, and permanent exclusions

Continue to Document 4 (Party Kits) for the complete 40-page Party Kit specification—PoshPet's core differentiator.

Continue to Document 5 (Legal & Technical Architecture) for compliance, database master list, and deployment.

POSHPET

Phase 1 Technical Documentation

Document 4 of 5: Party Kits

PoshPet's Core Differentiator

Time Capsules | Living Memory Pages | Care Circle Contributions
Intelligent Pacing | Cinematic Completion | Legacy Archive

4 Launch Kits | 8 Step Types | Complete Database & API Specs

Version 3.0 | February 2026

5.14 PARTY KITS — POSHPET'S CORE DIFFERENTIATOR

Party Kits are guided celebration experiences that transform pet milestones into lasting, emotional memories. No other pet app offers anything like this. Party Kits are the primary reason users upgrade to Premium, the primary retention mechanism (Time Capsules lock users in for 12+ months), and the primary emotional differentiator that makes PoshPet impossible to replace.

A Party Kit is not a checklist. It is a curated, multi-step journey that guides the user through preparing for, celebrating, and preserving a milestone in their pet's life. Each step is designed with specific emotional intent, paced intelligently over days or weeks, and culminates in a cinematic completion experience.

5.14.1 What Makes Party Kits Different

Five innovations that no competitor offers:

- 1. Time Capsules:** Users record voice or video messages that are encrypted, sealed with a wax-stamp animation, and delivered exactly one year later. A birthday message recorded in March 2026 arrives in March 2027 as a surprise. This creates 12-month minimum retention lock-in.
- 2. Living Memory Pages:** Each completed kit generates a beautiful, scrollable Memory Page that grows across years. A pet's 3rd birthday page shows contributions from all three years. These become irreplaceable digital keepsakes.
- 3. Care Circle Contributions:** Family and friends contribute photos, messages, and voice notes to celebration Memory Pages through Care Circles. Grandma records a voice message. The kids draw a picture. These are assembled into a shared celebration memory.
- 4. Intelligent Pacing:** AI-powered step delivery that adapts to user behavior. If the birthday is March 15, steps begin arriving March 1 with escalating emotional intensity. Users who engage quickly get faster delivery. Users who need time get gentler pacing.
- 5. Legacy Celebration Archive:** All completed kits are permanently preserved in a Legacy Archive. When a pet passes, these become the foundation of Memorial Mode—years of intentional celebrations that tell the story of a life well-loved.

5.14.2 Architecture Overview

Party Kits have two layers: the template layer (built by developer, managed by founder via admin panel) and the user experience layer (what the user sees and interacts with).

Template Layer (Developer Builds)

Kit Template: Defines the kit identity: name, description, icon, target event type, number of steps.

Step Templates: Each step within a kit: order, step type, prompt text, emotional copy, UI configuration, timing offset from target date.

Step Types: 8 reusable input types that steps can use (detailed in 5.14.4).

Completion Config: Animation style, celebration copy, Memory Page layout for this kit.

Founder Control Layer (Admin Panel)

The founder can manage kits without code deploys:

Edit step text: Change prompts, emotional copy, hint text

Reorder steps: Drag and drop to rearrange

Toggle kits: Enable/disable specific kits

Preview: Step-through the entire kit as a user would see it

Add new kits: Create new kits from step type building blocks (no developer needed after Phase 1 launch)

User Experience Layer

What the user interacts with:

Kit Discovery: Available kits shown on pet profile based on pet data (birthday set = Birthday Kit available).

Kit Start: User taps to begin. First step appears immediately.

Step Progression: Steps delivered according to intelligent pacing based on target date.

Step Completion: Each step has its own micro-celebration when completed.

Kit Completion: Cinematic 8-10 second experience when all steps done.

Memory Page: Beautiful, scrollable page generated from all responses.

Legacy Archive: All completed kits accessible forever.

5.14.3 Phase 1 Kits — 4 Total

Phase 1 launches with 4 carefully designed celebration kits. Each kit targets a specific milestone that pet parents care about deeply.

KIT 1: BIRTHDAY CELEBRATION

Kit ID: birthday_celebration

Target Event: Pet's birthday (requires birthday date in pet profile)

Availability: Appears 14 days before pet's birthday each year

Steps: 7 total

Estimated completion time: 5-10 minutes spread across 7-14 days

Premium features: Time Capsule (step 5), Circle Contributions (step 6), Full Memory Page

Free experience: Basic checklist version with steps 1-4 only, simplified Memory Page (photo + date only)

Emotional arc: Reflection → Gratitude → Celebration → Preservation

#	Step Title	Type	User Prompt / Description	UI Notes
1	Set the Date	date_picker	"When is [Pet]'s birthday? Let's start planning something special."	Calendar picker. Pre-fills if birthday in profile. Teal 'Confirmed!' animation on set.
2	This Year's Photo	photo_capture	"Snap a fresh birthday portrait of [Pet]. This becomes the cover of their Memory Page."	Camera opens directly. Gallery option available. Crop to 4:3 ratio. Preview with 'Perfect!' overlay.
3	A Year of Growth	text_input	"What's the biggest way [Pet] has grown or changed this year? A new trick? A funny habit? A deeper bond?"	Text area, 500 chars max. Hint: 'Take a moment to think about the past year...' Canela serif header.
4	Birthday Wish	text_input	"If [Pet] could understand one message from you today, what would it be?"	Text area, 300 chars max. Emotional copy below: 'These words become part of [Pet]'s permanent story.' Soft golden glow border.
5	Time Capsule Message	voice_video	"Record a birthday message for [Pet]. You'll hear this again in exactly one year." (PREMIUM)	Voice (30s) or Video (30s) toggle. Recording UI with countdown timer. Preview before sealing. Seal animation plays after confirmation. ENCRYPTED immediately.
6	Circle Love	circle_contribution	"Invite your family and friends to add their birthday wishes." (PREMIUM)	Circle selector. Set deadline (1-14 days). Members get notification. Contributions collected asynchronously.

				Creator previews before finalizing.
7	Celebration!	completion	Kit complete. Cinematic animation triggers. Memory Page generated.	8-second animation: cake with candles, confetti burst, 'Happy Birthday [Pet]!' in gold Canela text. Memory Page link appears.

Birthday Kit Emotional Copy:

Step 1 intro screen: "Another year of unconditional love. Another year of morning greetings, evening cuddles, and everything in between. Let's celebrate."

Step 3 hint text: "Maybe they finally stopped chewing shoes. Maybe they learned to trust you after a rough start. Maybe they just kept being perfect."

Step 5 pre-record screen: "A year from now, you'll hear your own voice saying these words. You'll remember exactly how you felt today. This is a gift to your future self."

Completion screen: "This birthday isn't just a date. It's proof that love shows up every single day. Happy Birthday, [Pet]."

KIT 2: ADOPTION ANNIVERSARY**Kit ID:** adoption_anniversary**Target Event:** Pet's adoption date (requires adoption_date in pet profile)**Availability:** Appears 14 days before adoption anniversary each year**Steps:** 6 total**Estimated completion time:** 5-8 minutes spread across 5-14 days**Premium features:** Time Capsule (step 4), Circle Contributions (step 5), Full Memory Page**Free experience:** Steps 1-3 only, simplified Memory Page*Emotional arc: Origin story → Journey → Bond → Future → Preservation*

#	Step Title	Type	User Prompt / Description	UI Notes
1	Gotcha Day Date	date_picker	"When did [Pet] officially become yours? Let's honor the day everything changed."	Calendar picker. Pre-fills from adoption_date. 'Saved!' with heart animation.
2	The Day We Met	text_input	"Tell the story. Where were you? What did [Pet] look like? What made you know?"	Text area, 500 chars max. Hint: 'Every great love story has a beginning.' Warm peach border.
3	Then vs Now	photo_capture	"Find or take a photo that shows how far you've both come."	Camera + gallery. Optional: side-by-side template if user has older photo in gallery. Caption field below.
4	A Promise Forward	voice_video	"Record a message about what you hope for next year together." (PREMIUM)	Voice/video toggle, 30s max. Pre-record copy: 'Future you will hear this and smile.' Seal animation on confirm.
5	Family Reflections	circle_contribution	"Invite the people who've watched your journey together." (PREMIUM)	Circle selector + deadline. Contribution prompt: 'Share a memory or message about [Pet] and [Owner].'
6	Anniversary Complete	completion	Cinematic completion. Memory Page generated.	8-second animation: intertwined hearts growing from seedling, 'Forever Chosen' text. Memory Page link.

Adoption Anniversary Emotional Copy:*Step 1 intro: "You didn't just adopt a pet. You chose a family member. Let's celebrate the day that choice was made."**Step 2 hint: "Was it at a shelter? A rescue? A friend's litter? The best stories start with 'I wasn't even planning to...'"**Step 4 pre-record: "One year from today, you'll hear yourself talking about hopes and dreams for your life together. Those words will mean everything."*

Completion: "Chosen. Every single day since that first day. That's what adoption means."

KIT 3: NEW PET WELCOME**Kit ID:** new_pet_welcome**Target Event:** Pet added to PoshPet within last 30 days**Availability:** Appears immediately when new pet is created. Available for 30 days.**Steps:** 6 total**Estimated completion time:** 3-5 minutes, can be done in one session**Premium features:** Time Capsule (step 4), Circle Contributions (step 5), Full Memory Page**Free experience:** Steps 1-3 only, simplified Memory Page*Emotional arc: Excitement → First impressions → Hopes → Time capsule → Community welcome*

#	Step Title	Type	User Prompt / Description	UI Notes
1	Welcome Photo	photo_capture	"Take [Pet]'s very first PoshPet portrait. This is Day One."	Camera priority (gallery secondary). Full-screen capture. 'Welcome home!' overlay with sparkles.
2	How We Found Each Other	single_choice	"How did [Pet] come into your life?"	Options: Breeder, Shelter/Rescue, Friend/Family, Found/Stray, Pet Store, Other. Selection triggers tailored follow-up text.
3	First Impressions	text_input	"Describe [Pet] in 3 words. What's the very first thing you noticed?"	Three separate text fields (one word each). Below: larger text area for 'first thing noticed' (200 chars).
4	Message to Future You	voice_video	"Record a message to yourself. One year from now, you'll hear how you felt at the very beginning." (PREMIUM)	Voice/video, 30s. Pre-record: 'The first days are magic. Capture that feeling before it becomes routine.' Seal animation.
5	Welcome Committee	circle_contribution	"Let your family and friends officially welcome [Pet]." (PREMIUM)	Circle selector. Contribution prompt: 'Welcome [Pet] to the family! Share a message or photo.'
6	Welcome Complete	completion	Cinematic completion. Memory Page generated.	6-second animation (shorter than birthday—it's a beginning, not a celebration of time): door opens with warm light, paw prints walk in, 'Welcome Home, [Pet]' text.

New Pet Welcome Emotional Copy:*Step 1 intro: "Every great story has a first chapter. This is yours and [Pet]'s. Let's make it count."**Step 3 hint: "Was it the eyes? The way they tilted their head? The fact that they chose YOU?"*

Step 4 pre-record: "You'll forget the chaos of the first week. You won't forget how this message makes you feel a year from now."

Completion: "Welcome home, [Pet]. The adventure starts now. And PoshPet will be here for every step."

KIT 4: SENIOR PET COMFORT

Kit ID: senior_pet_comfort

Target Event: Pet age reaches 'senior' threshold (dogs 7+, cats 10+, varies by species)

Availability: Appears when pet enters senior age range. Repeatable annually.

Steps: 6 total

Estimated completion time: 5-8 minutes spread across 5-14 days

Premium features: Time Capsule (step 5), Full Memory Page

Free experience: Steps 1-3 only, simplified Memory Page

Emotional arc: Acknowledgment → Reflection → Adaptation → Gratitude → Promise → Preservation

IMPORTANT DESIGN NOTE: This kit is the most emotionally sensitive. The tone must be warm and honoring, never sad or morbid. This celebrates the depth of a long relationship, not the approach of loss.

#	Step Title	Type	User Prompt / Description	UI Notes
1	Senior Portrait	photo_capture	"[Pet]'s face tells a story now. The gray muzzle. The knowing eyes. Capture this beautiful chapter."	Camera + gallery. Warm filter preset available (optional). Soft golden border on preview.
2	The Golden Years	text_input	"What's the best part about knowing [Pet] this deeply? What do you understand now that you didn't in the beginning?"	Text area, 500 chars. Hint: 'After all these years, what does [Pet] teach you just by being there?' Warm amber border.
3	Comfort Adjustments	multi_choice	"How have you adapted [Pet]'s care for their golden years?"	Checkboxes: Softer bed/sleeping area, Shorter walks, Ramp/stairs assist, Diet changes, More frequent vet visits, Extra cuddle time, Supplements, Other (text field). Tracks care evolution.
4	A Lifetime of Moments	single_choice	"If you could relive one moment with [Pet], which would it be?"	Options: A specific adventure, A lazy Sunday, The day we met, A funny incident, A quiet evening together. Follow-up text field to describe.
5	Words for the Journey	voice_video	"Record a message. Not for the future. For right now. Say what [Pet] means to you today." (PREMIUM)	Voice/video, 30s. Pre-record: 'The walks are slower now. The naps are longer. But the love? It's deeper than ever.' This capsule delivers in 6 months (not 12) given senior age context. Seal animation.

6	Honoring the Journey	completion	Cinematic completion. Memory Page generated.	10-second animation (longest kit—deserves reverence): Montage-style transitions of paw prints growing larger then softening, warm golden light, 'A Lifetime of Love' text in elegant gold. Gentle piano note.
---	----------------------	------------	--	---

Senior Pet Comfort Emotional Copy:

Step 1 intro: "The walks are slower now. The naps are longer. But the love? It's deeper than ever. Let's honor this chapter."

Step 2 hint: "Maybe it's the way they know your mood before you do. Maybe it's how they still greet you at the door, even when it takes them a little longer."

Step 4 follow-up: "Close your eyes for a moment. See it. Feel it. That's yours forever."

Completion: "Not every love story is measured in years. Yours is measured in walks, in meals, in quiet moments on the couch. And every single one mattered."

5.14.4 Step Types (8 Total)

Step types are the reusable input components that kit steps are built from. Each type has specific UI, validation, and storage requirements. New kits created via admin panel can mix and match any of these 8 types.

TYPE 1: date_picker

Purpose: Capture a specific date (birthday, anniversary, target date)

UI: Native date picker. Calendar view with month navigation. Pre-fills from pet profile if relevant date exists. Teal highlight on selected date.

Validation: Must be a valid date. Cannot be in the future for past events (birthdays). Cannot be more than 30 years in the past.

Storage: ISO 8601 date string in step response JSONB

Completion animation: Calendar icon pulses, date text appears with gentle fade, teal checkmark

TYPE 2: yes_no

Purpose: Simple binary question

UI: Two large buttons side by side: 'Yes' (teal) and 'No' (outlined). Optional follow-up text field that appears based on selection.

Validation: One option must be selected

Storage: Boolean + optional text string in JSONB

Completion animation: Selected button pulses, gentle checkmark

TYPE 3: text_input

Purpose: Capture written reflections, stories, wishes

UI: Text area with character counter. Hint text below in italics. Border color: warm peach or gold depending on kit context. Optional Canela serif header above.

Validation: Minimum 10 characters, maximum configured per step (200-500). Required unless step configured as optional.

Storage: Text string in JSONB

Completion animation: Text 'locks in' with subtle shimmer effect across the text, then checkmark

TYPE 4: single_choice

Purpose: Select one option from a list

UI: Vertical list of options, each as a card (full width, 56px height, 12px border radius). Tap to select (teal border + fill background at 10%). Selected option shows teal checkmark. If 'Other' option present, text field appears below.

Validation: One option required

Storage: Selected option key + optional text in JSONB

Completion animation: Selected card pulses, others fade slightly

TYPE 5: multi_choice

Purpose: Select multiple options from a list

UI: Same card layout as single_choice but with checkboxes. Multiple selections allowed. Minimum 1 selection required. 'Other' option with text field if configured.

Validation: At least 1 selection required

Storage: Array of selected option keys + optional text in JSONB

Completion animation: All selected cards pulse simultaneously

TYPE 6: photo_capture

Purpose: Capture or select a photo for the celebration

UI: Large camera viewfinder (80% screen height). Capture button centered at bottom. Gallery icon in bottom-left corner. After capture: preview with 'Use This Photo' and 'Retake' buttons. Crop tool available (4:3 for Memory Page display). Caption field below preview (200 chars, optional).

Validation: One photo required. JPEG/PNG/HEIC. Max 10MB.

Storage: Photo URL (processed through standard pipeline: thumbnail, medium, original) + caption in JSONB

Completion animation: Photo drops into a frame with gold border, gentle 'click' sound

TYPE 7: voice_video (Premium Only)

Purpose: Record Time Capsule voice memo or video message

UI details: Covered in detail in section 5.14.5 (Time Capsule System)

Voice mode: Waveform visualizer during recording. 30-second max. Countdown timer. Preview playback before sealing.

Video mode: Front camera active. 30-second max with countdown. 720p resolution. Preview playback before sealing.

Validation: Minimum 3 seconds, maximum 30 seconds

Storage: Encrypted media URL + duration + type in JSONB

Completion animation: Seal animation (see 5.14.5)

TYPE 8: circle_contribution (Premium Only)

Purpose: Invite Care Circle members to contribute to this celebration

UI details: Covered in detail in section 5.14.7 (Care Circle Contributions)

Interface: Circle selector, deadline setter, contribution tracker showing who has/hasn't contributed

Validation: At least 1 circle selected, deadline set

Storage: Circle IDs, deadline, contribution references in JSONB

Completion animation: Contributors' avatars float in one by one, assembling into a group, then heart burst

5.14.5 Time Capsule System

Time Capsules are PoshPet's most powerful retention feature. A user records a voice or video message, it is sealed with an animated wax stamp, encrypted, and delivered exactly one year later as a surprise. This creates a minimum 12-month retention hook—users cannot receive their capsule if they cancel.

Recording Interface

Voice Mode:

Screen layout: Dark background (charcoal #333333) for recording focus. Centered circular waveform visualizer (200px diameter) that reacts to voice amplitude in real-time. Below: red record button (56px, pulsing glow when active). Timer counting up from 0:00 to 0:30 in 16px white text. 'Tap to start' label before recording begins.

Controls: Tap to start recording. Tap again to stop. Stop automatically at 30 seconds.

Quality: MP3, 128kbps, mono. Noise reduction applied if available on device.

Post-recording: Play/pause preview. Re-record button. 'Seal This Message' primary button.

Video Mode:

Screen layout: Front camera viewfinder fills screen. Countdown timer overlay (30 seconds). Red record indicator dot (top-right). 'Tap to record' overlay before starting.

Controls: Tap to start. Tap to stop. Auto-stops at 30 seconds.

Quality: MP4, 720p, H.264. Front camera only (this is personal, intimate).

Post-recording: Full playback preview. Re-record button. 'Seal This Message' primary button.

Seal Flow

After user taps 'Seal This Message':

Confirmation modal: 'Once sealed, this message cannot be opened until [delivery date]. Are you sure?' with delivery date shown prominently. 'Seal It' (primary) and 'Go Back' (secondary) buttons.

On confirm: Seal animation begins (see below). During animation, file is uploaded and encrypted on backend.

Seal Animation (2 seconds):

0.0s: Message represented as a cream-colored envelope slides to center of screen

0.3s: Envelope flap folds closed

0.5s: Red wax blob drops from above onto envelope flap (gravity physics)

0.8s: Ornate seal stamp presses into wax (with slight squish deformation)

1.2s: Stamp lifts, revealing PoshPet paw print embossed in wax

1.5s: Wax hardens with subtle shine/gloss effect

1.8s: Delivery date text fades in below: 'Delivers: March 15, 2027'

2.0s: Complete. Envelope gently pulses once. Soft chime sound.

After seal: 'Your message is safe. See you in one year.' confirmation text. Return to kit flow.

Encryption

Algorithm: AES-256-GCM

Key management: Unique encryption key per capsule. Key stored separately from encrypted media. Key cannot be accessed before delivery date without backend override.

Storage: Encrypted files in dedicated S3/R2 bucket (separate from regular photos). Bucket policy: no public access, signed URLs only, generated on-demand at delivery time.

Metadata: Capsule metadata (delivery date, pet ID, kit ID, recording duration) stored in PostgreSQL. Actual media stored in object storage.

Integrity: SHA-256 hash stored at seal time. Verified at delivery to ensure no tampering.

Delivery System

Delivery Trigger:

Cron job runs daily at 9:00 AM UTC. Checks all sealed capsules where `delivery_date <= today` AND `status = 'sealed'`. For each matching capsule, triggers delivery flow.

Delivery Flow:

Step 1: Push notification: 'A message from the past is waiting for you... ' (high priority, overrides quiet hours if enabled)

Step 2: In-app: sealed envelope appears on pet's profile with pulsing glow

Step 3: User taps envelope to begin unseal

Step 4: Unseal animation plays (3 seconds—see below)

Step 5: Original recording plays automatically

Step 6: After playback: 'This message was recorded on [seal date]' with context of which kit/celebration it came from

Step 7: Options: Replay, Save to Camera Roll, Share to Circle, Return to Profile

Unseal Animation (3 seconds):

0.0s: Sealed envelope centered on screen, warm golden glow builds behind it

0.3s: Wax seal begins to glow red, then starts melting/cracking

0.8s: Seal breaks apart with small particle effect (wax fragments)

1.2s: Envelope flap begins to open, golden light beams from inside

1.8s: Envelope fully open, light intensifies briefly

2.3s: Recording player UI fades in over the golden glow

2.5s: Context text: 'Recorded [date], during [Pet]'s [event name]'

3.0s: Auto-play begins

Early Release on Pet Passing:

If a user activates Memorial Mode (pet marked as passed away), ALL sealed Time Capsules for that pet are immediately released. Delivery notification is modified: 'We have messages waiting for you.' No celebration animation—quiet, respectful presentation. Unseal animation is gentler

(slower, softer golden glow, no crack/break effects). This ensures no user ever loses a Time Capsule due to pet loss.

5.14.6 Living Memory Pages

Living Memory Pages are the tangible output of a completed Party Kit. Each page is a beautiful, scrollable, shareable record of a celebration. The 'living' aspect means pages grow across years—a pet's birthday page shows Year 1, Year 2, Year 3, each with that year's responses, photos, and contributions.

Page Structure

Header Section:

Background: Soft gradient (kit-specific colors). Birthday = gold-to-peach. Adoption = rose-to-cream. Welcome = teal-to-cream. Senior = amber-to-cream.

Title: Kit name in Canela serif, 28px, centered. 'Birthday Celebration' or 'Adoption Anniversary'

Pet name: Below title, 20px, Canela serif

Year badge: Circular badge showing celebration year: 'Year 3' or '2026'

Pet photo: Circular, 120px diameter, from the photo_capture step of this kit

Content Section:

Each step's response displayed in order as styled cards:

Text responses: In elegant serif font (Canela), with decorative quotation marks. Displayed as pull-quote style.

Photo responses: Full-width image with subtle rounded corners (12px) and optional caption below in italics.

Choice responses: Displayed as styled text: 'How [Pet] came into your life: Shelter Rescue'

Voice/Video indicator: Time Capsule section showing sealed status with delivery date OR play button if delivered/opened

Contributions Section (Premium):

If circle contributions were collected:

Section header: 'Messages from [Circle Name]' in Canela serif

Each contribution: Contributor avatar (40px circle), name, timestamp. Text message in serif. Photo in rounded frame. Voice note with play button and duration.

Layout: Masonry-style for visual variety, alternating left/right alignment

Footer:

Time Capsule indicator: If capsule sealed: 'A Time Capsule is sealed for this celebration. Delivers [date].' with small envelope icon

Share button: 'Share This Memory' — generates shareable image or link

Export button: 'Download as PDF' (Premium) — formatted for printing

Year-Over-Year Navigation

When a pet has multiple years of the same celebration (e.g., 3 birthdays), the Memory Page becomes navigable:

Navigation: Horizontal swipe between years. Year indicators at top: dots or year numbers. Current year highlighted in teal.

Comparison view: Optional side-by-side toggle showing photos from different years

Growth story: Auto-generated header: 'Year 3 of celebrating [Pet]'s birthday'

This year-over-year accumulation is what makes Memory Pages 'living'—they're not static. Every year adds a new layer to the story.

Export Options

Share Image: Generate 1080×1920px image (Instagram Story format) with Memory Page highlights: pet photo, celebration title, one text quote, PoshPet branding

Full PDF (Premium): Multi-page formatted PDF with all responses, photos, and contributions. Cover page with pet photo, title, dates. Formatted for A4/Letter printing.

Multi-Year PDF (Premium): Combined PDF showing all years of one celebration type. Chapter per year. Table of contents.

5.14.7 Care Circle Contributions

Circle contributions allow family and friends to participate in celebrations. This transforms Party Kits from a solo experience into a shared family memory.

Invitation Flow

Step 1: Kit creator reaches the circle_contribution step in their kit

Step 2: Screen shows list of circles the user belongs to. Select one or more circles.

Step 3: Set deadline for contributions (date picker, 1-14 days from now). Default: 7 days.

Step 4: Customize contribution prompt (pre-filled with kit-specific text, editable). Example: 'Share a birthday message or photo for [Pet]!'

Step 5: Tap 'Send Invitations'. Confirmation: '[X] circle members will be notified.'

Contributor Experience

When a circle member receives an invitation:

Push notification: '[Owner] is celebrating [Pet]'s birthday! Add your message 🎉'

In-app card: Special card in circle feed with warm gold border. Shows: pet photo, celebration type, deadline countdown, 'Add My Contribution' button.

Contribution options: Text message (500 chars max), Photo (camera or gallery, with optional caption), Voice note (30 seconds max). One contribution per member per kit (can edit/replace until deadline).

Confirmation: 'Your message for [Pet] has been saved! [Owner] will see it when the celebration is complete.'

Deadline Handling

Active period: Contributors can add/edit until deadline

24-hour warning: Notification to members who haven't contributed: 'Last chance to add your message for [Pet]'s birthday!'

Deadline reached: Contributions locked. Creator notified: 'All contributions are in! Ready to complete your celebration.'

Manual close: Creator can close contributions early if satisfied with submissions

No contributions: If no circle members contribute, step is marked as 'Completed without contributions' and Memory Page simply omits the contributions section. No error, no penalty.

Assembly Preview

Before finalizing the kit, the creator sees a preview of all contributions:

Preview screen: Shows each contribution with contributor avatar and name. Creator can: reorder contributions, hide inappropriate content (with notification to contributor), add their own note to the collection.

Finalize: 'Complete Celebration' button commits all contributions to the Memory Page permanently.

5.14.8 Intelligent Ritual Pacing

Party Kits are not meant to be completed in one sitting (though they can be). The pacing system delivers steps over time, building anticipation and emotional investment as the celebration date approaches.

Base Timing Algorithm

Steps are distributed between kit start date and target event date:

Available window: Kit becomes available 14 days before target date

Step spacing: Steps distributed evenly across available window, with acceleration near the end

Example — Birthday Kit (7 steps, birthday March 15):

Step 1 (Set Date): Available immediately on kit start (March 1)

Step 2 (Photo): Available March 3

Step 3 (Year of Growth): Available March 5

Step 4 (Birthday Wish): Available March 8

Step 5 (Time Capsule): Available March 10

Step 6 (Circle Contributions): Available March 11 (needs time for others to respond)

Step 7 (Completion): Available March 14 (day before birthday) or March 15

Note: All steps are immediately completable once available. The pacing system controls when notification prompts are sent, not when steps unlock. If a user wants to complete all steps in day one, they can.

User Behavior Adaptation

Fast engager: If user completes steps same-day as notification, system delivers next step sooner (within 24 hours instead of waiting for scheduled date).

Slow engager: If user doesn't complete a step within 48 hours, send gentle nudge: '[Pet]'s birthday celebration is waiting for you.' If still no engagement after 72 hours, reduce nudge frequency to avoid nagging.

Last-minute rusher: If target date is 2 days away and user has completed 0 steps, switch to rapid delivery: all steps available immediately with encouraging copy: 'It's not too late to make this special!'

Abandoned kit: If no interaction for 7+ days and target date has passed, mark kit as 'expired' with option to restart next year. No shame messaging.

Notification Integration

Pacing notifications follow the Smart Notification rules (5.11):

Delivery: One kit notification per day maximum

Time: Delivered during user's typical engagement window (learned from Invisible AI patterns)

Copy escalation: Early steps: casual and inviting. Mid steps: warm and encouraging. Final steps: gently urgent and emotional.

Quiet hours: Respected. Kit notifications held until quiet hours end.

Example progression:

Day 1: 'Ready to start planning [Pet]'s birthday? 🎂'

Day 5: '[Pet]'s birthday celebration is coming along beautifully. Next step is ready!'

Day 10: 'Have you recorded your Time Capsule yet? This is the part that makes you cry next year 🧡'

Day 13: 'Tomorrow is the big day! One step left to make it perfect.'

5.14.9 Cinematic Completion Experience

When ALL kit steps are complete, the cinematic completion experience fires. This is the emotional climax of the entire Party Kit journey. It must feel earned, beautiful, and unforgettable. Users should want to complete kits just to experience this moment.

Universal Completion Structure (8-10 seconds)

Beat-by-beat timeline:

0.0 - 0.5s: Screen dims to 70% with soft vignette. All UI elements fade out. Sound: soft ambient tone begins.

0.5 - 2.0s: Kit-specific hero animation plays center screen (see per-kit animations below). Fills approximately 60% of screen width.

2.0 - 3.0s: Hero animation settles. Confetti or particles burst from animation outward (40-60 particles, kit-specific colors).

3.0 - 4.5s: Emotional headline text fades in above animation. Canela serif, gold (#FFD700), 28px. Kit-specific copy.

4.5 - 5.5s: Pet name text fades in below headline. 20px, white, Canela serif.

5.5 - 7.0s: Memory Page preview card slides up from bottom. Shows miniature version of the generated page with pet photo, title, year.

7.0 - 8.0s: Action buttons fade in: 'View Memory Page' (primary, teal), 'Share' (secondary), 'Close' (text link).

8.0 - 10.0s: Ambient particles continue floating. Background music loop plays softly if sound enabled.

Kit-Specific Hero Animations

Birthday Celebration:

3D-style birthday cake rotates slowly to front-facing position. Candles flicker with warm glow. At peak moment, candles blow out with sparkle trail rising from each. Confetti colors: gold, peach, cream, teal. Sound: soft 'happy birthday' music box melody (5 seconds).

Adoption Anniversary:

Two silhouettes (pet and person) start at opposite sides of screen. Walk/move toward each other. Meet in center. Merge into single heart shape that glows and pulses. Particles: rose gold and soft pink. Sound: gentle string swell.

New Pet Welcome:

Door shape in center of screen (wooden, warm tones). Door opens outward with light flooding out. Small paw prints walk through the door from background to foreground. Leave sparkle trail. Particles: teal and cream. Sound: warm chime ascending.

Senior Pet Comfort:

Golden sunrise fills screen from bottom to top (warm amber gradient). Silhouette of pet resting peacefully in foreground. Small stars appear one by one around the silhouette (each representing a year). Final star is brightest. Particles: gold and warm amber. Sound: gentle piano notes ascending slowly. THIS IS THE LONGEST ANIMATION (10 seconds) because it deserves reverence.

Free vs Premium Completion

Element	Free	Premium
Hero animation	Simplified version (static image, no particles)	Full cinematic animation
Confetti/particles	None	Full particle system
Sound	None	Kit-specific sound
Memory Page preview	Basic (photo + date only)	Full preview (all responses, contributions)
Share button	Not available	Available
Emotional copy	Generic: 'Celebration complete!'	Kit-specific emotional headline
View Memory Page	Basic version link	Full version link
Upgrade prompt	'Upgrade to unlock Time Capsules and full celebrations'	Not shown

5.14.10 Legacy Celebration Archive

Every completed Party Kit is permanently preserved in the Legacy Celebration Archive. This archive is the long-term emotional anchor of PoshPet—years of intentional celebrations that document a pet's entire life.

Archive Location

Access: Pet Profile > 'Celebrations' tab

Layout: Grid of completed celebration cards, newest first. Each card shows: celebration icon, title ('Birthday 2026'), pet photo from that kit, completion date.

Empty state: Encouraging illustration with 'No celebrations yet. Your first Party Kit awaits!' and link to available kits.

Archive Features

View any Memory Page: Tap card to view full Memory Page for that celebration

Year-over-year view: For repeating celebrations (birthdays, anniversaries), option to view all years in sequence

Time Capsule status: Each card shows capsule indicator: sealed (locked icon), delivered (opened icon), or no capsule

Statistics: Archive header shows: 'X celebrations completed' and 'X years of memories'

Memorial Transformation

When Memorial Mode is activated for a pet:

Archive becomes memorial centerpiece: Renamed to 'Celebration Memories' with memorial styling (sepia tones, soft borders)

Chronological reorder: Archive switches to chronological (oldest first) to tell the life story in order

Memorial summary: Auto-generated text: '[Pet Name] — [X] birthdays celebrated, [X] anniversaries honored, [X] years of love.'

Export: 'Download Complete Celebration Archive' as a single multi-section PDF with all Memory Pages

Sharing: Each Memory Page can be shared individually or entire archive can generate a memorial link

5.14.11 Database Schema

The Party Kit system requires 7 interrelated tables:

Kit Templates (Admin-Managed)

```
CREATE TABLE party_kit_templates (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  kit_type VARCHAR(50) NOT NULL UNIQUE, -- 'birthday_celebration', etc.
  name VARCHAR(100) NOT NULL,
  description TEXT,
  icon VARCHAR(50),
  target_event_type VARCHAR(50), -- 'birthday', 'adoption', 'new_pet',
  'senior'
  total_steps INTEGER NOT NULL,
  days_before_available INTEGER DEFAULT 14,
  is_active BOOLEAN DEFAULT TRUE,
  is_premium_only BOOLEAN DEFAULT FALSE,
  free_step_limit INTEGER DEFAULT 4, -- how many steps free users can access
  completion_animation_id VARCHAR(50),
  completion_headline TEXT,
  completion_subtext TEXT,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  updated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);
```

Step Templates (Admin-Managed)

```
CREATE TABLE party_kit_steps (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  kit_template_id UUID NOT NULL REFERENCES party_kit_templates(id) ON DELETE
  CASCADE,
  step_order INTEGER NOT NULL,
  step_type VARCHAR(30) NOT NULL, -- 'date_picker', 'text_input',
  'photo_capture', etc.
  title VARCHAR(200) NOT NULL,
  prompt_text TEXT NOT NULL,
  hint_text TEXT,
  emotional_intro_text TEXT, -- shown before step input
  emotional_completion_text TEXT, -- shown after step complete
  is_premium_only BOOLEAN DEFAULT FALSE,
  config JSONB, -- step-type-specific config (options for choices, max_length
  for text, etc.)
  timing_offset_days INTEGER, -- days before target date this step should be
  prompted
  UNIQUE(kit_template_id, step_order)
);
```

User Kit Progress

```
CREATE TABLE user_kit_progress (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
```

```

    user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
    pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
    kit_template_id UUID NOT NULL REFERENCES party_kit_templates(id),
    target_date DATE, -- the celebration date
    celebration_year INTEGER, -- which year of this celebration (1, 2, 3...)
    status VARCHAR(20) DEFAULT 'active', -- 'active', 'completed', 'expired',
    'abandoned'
    current_step INTEGER DEFAULT 1,
    started_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
    completed_at TIMESTAMP WITH TIME ZONE,
    memory_page_url VARCHAR(500),
    UNIQUE(user_id, pet_id, kit_template_id, celebration_year)
);
CREATE INDEX idx_kit_progress_user ON user_kit_progress(user_id, status);
CREATE INDEX idx_kit_progress_pet ON user_kit_progress(pet_id, status);

```

User Step Responses

```

CREATE TABLE user_kit_step_responses (
    id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
    kit_progress_id UUID NOT NULL REFERENCES user_kit_progress(id) ON DELETE
    CASCADE,
    step_id UUID NOT NULL REFERENCES party_kit_steps(id),
    step_order INTEGER NOT NULL,
    response_data JSONB NOT NULL, -- all step data stored as JSON
    completed_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
    UNIQUE(kit_progress_id, step_id)
);

```

Time Capsules

```

CREATE TABLE time_capsules (
    id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
    user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
    pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
    kit_progress_id UUID REFERENCES user_kit_progress(id) ON DELETE SET NULL,
    media_type VARCHAR(10) NOT NULL, -- 'voice', 'video'
    encrypted_media_url VARCHAR(500) NOT NULL,
    encryption_key_id VARCHAR(100) NOT NULL, -- reference to key management
    system
    media_hash VARCHAR(64) NOT NULL, -- SHA-256 integrity hash
    duration_seconds INTEGER NOT NULL,
    status VARCHAR(20) DEFAULT 'sealed', -- 'sealed', 'delivered', 'opened',
    'released'
    sealed_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
    delivery_date DATE NOT NULL,
    delivered_at TIMESTAMP WITH TIME ZONE,
    opened_at TIMESTAMP WITH TIME ZONE,
    early_release_reason VARCHAR(50) -- 'memorial' if released due to pet
    passing
);

```

```
CREATE INDEX idx_capsules_delivery ON time_capsules(delivery_date, status)
WHERE status = 'sealed';
CREATE INDEX idx_capsules_pet ON time_capsules(pet_id, status);
```

Memory Pages

```
CREATE TABLE memory_pages (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  kit_progress_id UUID NOT NULL REFERENCES user_kit_progress(id) ON DELETE
  CASCADE,
  user_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  pet_id UUID NOT NULL REFERENCES pets(id) ON DELETE CASCADE,
  page_data JSONB NOT NULL, -- structured content: header, responses,
  contributions, footer
  share_image_url VARCHAR(500), -- generated 1080x1920 share image
  pdf_url VARCHAR(500), -- generated PDF export
  is_memorial BOOLEAN DEFAULT FALSE,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  updated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW()
);
```

Circle Contributions

```
CREATE TABLE circle_contributions (
  id UUID PRIMARY KEY DEFAULT gen_random_uuid(),
  kit_progress_id UUID NOT NULL REFERENCES user_kit_progress(id) ON DELETE
  CASCADE,
  circle_id UUID NOT NULL REFERENCES care_circles(id) ON DELETE CASCADE,
  contributor_id UUID NOT NULL REFERENCES users(id) ON DELETE CASCADE,
  contribution_type VARCHAR(20) NOT NULL, -- 'text', 'photo', 'voice'
  text_content TEXT,
  media_url VARCHAR(500),
  media_duration INTEGER, -- seconds for voice notes
  display_order INTEGER DEFAULT 0,
  is_hidden BOOLEAN DEFAULT FALSE, -- hidden by kit creator
  deadline DATE NOT NULL,
  created_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  updated_at TIMESTAMP WITH TIME ZONE DEFAULT NOW(),
  UNIQUE(kit_progress_id, circle_id, contributor_id)
);
```

5.14.12 API Endpoints

Kit Management

Method	Endpoint	Description
GET	/api/kits/available/{pet_id}	Get available kits for this pet (based on pet data, dates, eligibility)
GET	/api/kits/templates	Get all kit templates (admin)
GET	/api/kits/templates/{id}	Get kit template details with all steps (admin)
PUT	/api/kits/templates/{id}	Update kit template (admin)
PUT	/api/kits/templates/{id}/steps/reorder	Reorder steps (admin)
PUT	/api/kits/templates/{id}/toggle	Enable/disable kit (admin)

User Kit Progress

Method	Endpoint	Description
POST	/api/kits/start	Start a kit (body: pet_id, kit_template_id)
GET	/api/kits/progress/{pet_id}	Get all kit progress for a pet
GET	/api/kits/progress/{id}	Get specific kit progress with step responses
POST	/api/kits/progress/{id}/steps/{step_order}	Submit step response
PUT	/api/kits/progress/{id}/steps/{step_order}	Update step response (before kit complete)
POST	/api/kits/progress/{id}/complete	Complete kit (triggers animation, generates Memory Page)

Time Capsules

Method	Endpoint	Description
POST	/api/capsules	Create and seal a Time Capsule (upload media, encrypt)
GET	/api/capsules/{pet_id}	Get all capsules for a pet (sealed, delivered, opened)
GET	/api/capsules/{id}	Get capsule details (does NOT return media before delivery date)
POST	/api/capsules/{id}/open	Open delivered capsule (generates signed URL for decrypted media)
GET	/api/capsules/{id}/media	Stream decrypted media (only after delivery, signed URL)

Memory Pages

Method	Endpoint	Description
GET	/api/memory-pages/{pet_id}	Get all Memory Pages for a pet (archive view)
GET	/api/memory-pages/{id}	Get specific Memory Page with full content
GET	/api/memory-pages/{pet_id}/type/{kit_type}	Get all years of one celebration type
POST	/api/memory-pages/{id}/share-image	Generate shareable image
GET	/api/memory-pages/{id}/export	Generate PDF export (Premium)
GET	/api/memory-pages/{pet_id}/archive-export	Generate complete archive PDF (Premium)

Circle Contributions

Method	Endpoint	Description
POST	/api/contributions/invite	Send contribution invitation to circle(s)
GET	/api/contributions/{kit_progress_id}	Get all contributions for a kit (creator view)
POST	/api/contributions/{kit_progress_id}	Submit a contribution (circle member)
PUT	/api/contributions/{id}	Update contribution (before deadline)
PUT	/api/contributions/{id}/visibility	Show/hide contribution (creator)
PUT	/api/contributions/{kit_progress_id}/reorder	Reorder contributions (creator)
POST	/api/contributions/{kit_progress_id}/close	Close contributions early (creator)

5.14.13 Required Animation Files

File Name	Description	Duration	Max Size
kit_birthday_completion.json	Birthday cake, candle blow-out, sparkle trail	3000ms	800KB
kit_adoption_completion.json	Two silhouettes meeting, merging into heart	3000ms	800KB
kit_welcome_completion.json	Door opening, paw prints walking through, light	2500ms	800KB
kit_senior_completion.json	Golden sunrise, pet silhouette, accumulating stars	4000ms	1MB
kit_confetti_gold.json	Confetti particle system (gold/peach/cream/teal)	3000ms	300KB
kit_confetti_rose.json	Confetti particle system (rose gold/pink)	3000ms	300KB
kit_confetti_amber.json	Confetti particle system (gold/amber/warm)	3000ms	300KB
capsule_seal.json	Envelope fold, wax drop, stamp press, shine	2000ms	500KB
capsule_unseal.json	Wax melt, envelope open, golden light beams	3000ms	500KB
capsule_envelope_pulse.json	Sealed envelope idle pulse (for profile display)	2000ms loop	200KB
step_complete_shimmer.json	Generic step completion shimmer/checkmark	800ms	200KB

Total Party Kit animation files: 11. Combined maximum size: approximately 5.8MB.

5.14.14 Admin Panel Kit Management

The admin panel provides a visual interface for managing kits without code changes. This is critical for the solo founder to iterate on kit content based on user feedback.

Kit List View

Display: Table of all kit templates. Columns: Name, Type, Steps Count, Status (Active/Disabled), Completions Count, Completion Rate.

Actions: Edit, Preview, Toggle Active, Duplicate (for creating variations), View Analytics.

Kit Editor

Kit Settings:

Name: Editable text field

Description: Editable text area

Target event: Dropdown (birthday, adoption, new_pet, senior, custom)

Days before available: Number input (1-30)

Premium only: Toggle

Free step limit: Number input

Active: Toggle

Step Editor:

Visual step builder with drag-and-drop reordering:

Add step: Select step type from dropdown → new step card appears

Edit step: Click to expand. Edit: title, prompt text, hint text, emotional intro, emotional completion text, type-specific config (options for choices, max length for text, etc.)

Reorder: Drag handle on left side of step card

Delete step: Red delete icon with confirmation modal

Premium flag: Toggle per step to mark as premium-only

Preview Mode:

'Preview' button opens step-by-step walkthrough exactly as user would see it. Each step shows: emotional intro screen, input UI, completion animation. Allows testing the entire emotional arc before publishing.

Kit Analytics

Start rate: How many eligible users start this kit

Step completion funnel: Bar chart showing drop-off at each step

Average time to complete: Days from start to completion

Capsule seal rate: Percentage of kit completers who seal a Time Capsule

Circle contribution rate: Percentage who invite circles + average contributions received

Memory Page export rate: How many completed pages are shared or exported as PDF

END OF DOCUMENT 4: PARTY KITS

This document provides the complete specification for PoshPet's core differentiator:

- 5.14.1** — What makes Party Kits different (5 innovations)
- 5.14.2** — Architecture overview (template, founder control, user experience layers)
- 5.14.3** — 4 Phase 1 kits with complete step tables and emotional copy:
 - Birthday Celebration (7 steps)
 - Adoption Anniversary (6 steps)
 - New Pet Welcome (6 steps)
 - Senior Pet Comfort (6 steps)
- 5.14.4** — 8 step types with UI specs, validation, storage, and animations
- 5.14.5** — Time Capsule system: recording UI, seal flow, encryption, delivery, early release
- 5.14.6** — Living Memory Pages: structure, year-over-year navigation, export options
- 5.14.7** — Care Circle contributions: invitation flow, contributor experience, deadline handling
- 5.14.8** — Intelligent pacing: timing algorithm, behavior adaptation, notification integration
- 5.14.9** — Cinematic completion: 8-10 second timeline, 4 kit-specific animations, Free vs Premium
- 5.14.10** — Legacy Celebration Archive: storage, memorial transformation
- 5.14.11** — 7 database tables with complete schemas
- 5.14.12** — 30+ API endpoints across 5 endpoint groups
- 5.14.13** — 11 required animation files
- 5.14.14** — Admin panel kit management with visual editor and analytics

Continue to Document 5 (Legal & Technical Architecture) for compliance requirements, consolidated database schema, and deployment specifications.

POSHPET

Phase 1 Technical Documentation

Document 5 of 5: Legal & Technical Architecture

[Legal Compliance](#) | [Medical Disclaimers](#) | [Privacy & Data Protection](#)
[System Architecture](#) | [Database Master List](#) | [API Conventions](#) | [Deployment](#)

Version 3.0 | February 2026

PART 6: LEGAL & COMPLIANCE

This section covers all legal requirements, disclaimers, privacy policies, and compliance standards that must be implemented before launch. Consult a licensed attorney before finalizing legal text for production.

6.1 Medical Disclaimers

PoshPet's health tracking features (weight log, vet visit log, medication log) are observation-only tools. They do not diagnose, treat, or provide medical recommendations. Legal disclaimers are REQUIRED to protect the founder from liability.

6.1.1 Primary Disclaimer (Appears on All Health Screens)

"PoshPet Health Tracking is for personal observation and record-keeping only. It does not provide medical advice, diagnosis, or treatment recommendations. Always consult a licensed veterinarian for any health concerns about your pet. In case of emergency, contact your vet or emergency animal hospital immediately."

Placement Requirements:

Weight Log: Displayed in a subtle info banner (cream background, teal left border, 14px text) directly below the weight chart and above the entry form.

Vet Visit Log: Displayed as info banner at the top of the list view, below the page header.

Medication Log: Displayed as info banner below the medication list and above the 'Add Medication' button.

Styling: Non-dismissible. Always visible. Small medical cross icon (⚕) to the left of text. Text color: charcoal (#333333) at 14px size. Cannot be hidden by user settings.

6.1.2 First-Time Acknowledgment Screen

Before a user accesses ANY health feature for the first time, a full-screen modal must appear:

Screen Content:

Icon: Medical symbol centered at top (64px)

Heading: 'Important: Health Tracking Disclaimer' in Canela serif, 24px

Body text: [Full primary disclaimer text from 6.1.1 above]

Additional text: 'PoshPet does not replace professional veterinary care. Health logs are for your personal records only. Weight trends, medication tracking, and visit logs are not diagnostic tools.'

Checkbox: 'I understand that PoshPet Health Tracking is for personal observation only and does not provide medical advice.'

Button: 'I Understand' (disabled until checkbox checked). Teal primary button.

Storage: Acceptance stored as boolean in user record. Timestamp of acceptance logged. Never shown again after acceptance.

6.1.3 Weight Trend Disclaimer

When displaying weight trend arrows (up/down/stable), include footnote:

"Weight trends shown are based on your logged entries only. Consult your veterinarian about healthy weight ranges for your pet's breed and age."

6.1.4 Medication Disclaimer

On the medication setup screen:

"PoshPet medication tracking is a personal reminder tool only. It does not verify dosages, check drug interactions, or replace instructions from your veterinarian. Always follow your vet's prescribed dosage and schedule."

6.2 Terms of Service Summary

The full Terms of Service must be drafted by a licensed attorney. The following outlines key provisions to include:

6.2.1 Service Description

PoshPet is a pet care planning and celebration app. It provides task management, photo storage, health observation logs, and celebration tools. It does not provide veterinary advice, medical diagnosis, or professional pet care services.

6.2.2 User Responsibilities

Account accuracy: Users must provide accurate information

Content ownership: Users retain ownership of all uploaded photos, text, and recordings

Acceptable use: No harmful, illegal, or abusive content in Care Circles

Age requirement: Users must be 13+ years old (COPPA compliance). If targeting EU users, 16+ under GDPR.

6.2.3 PoshPet Responsibilities

Data protection: Secure storage of all user data using industry-standard encryption

Service availability: Reasonable efforts to maintain service uptime (no SLA guarantee for consumer app)

Content moderation: Remove reported content that violates community standards

Data deletion: Honor deletion requests within 30 days

6.2.4 Limitation of Liability

PoshPet is not liable for: health outcomes based on logged data, missed medication reminders, lost data beyond reasonable recovery efforts, actions of Care Circle members, or decisions made based on app information. PoshPet is not a substitute for professional veterinary care.

6.2.5 Subscription Terms

Free tier: Available indefinitely with feature limitations

Premium tier: Monthly or annual auto-renewing subscription

Cancellation: Cancel anytime. Access continues until end of current billing period.

Refunds: Handled per Apple/Google/Stripe policies

Price changes: 30-day notice before price increases for existing subscribers

Downgrade: When Premium expires, account reverts to Free tier. Data preserved but Premium features locked. Second pet and beyond become view-only. Time Capsules remain sealed until user re-subscribes or pet enters Memorial Mode.

6.3 Privacy Policy

6.3.1 Data Collected

Data Type	Required?	Purpose	Storage Duration
Email address	Yes	Authentication, account recovery, notifications	Until account deletion
Name	Yes	Display in app, Care Circle identification	Until account deletion
Pet information	Yes	Core app functionality (name, species, breed, birthday)	Until pet or account deletion
Pet photos	No	Gallery, timeline, Memory Pages	Until user deletes or account deletion
Health logs	No	Weight, vet visits, medication records	Until user deletes or account deletion
Voice/video recordings	No	Time Capsules only	Encrypted. Until capsule opened + 90 days, or account deletion
Task completion data	Auto	Streaks, garden, timeline, Invisible AI	Until account deletion
Device tokens	Auto	Push notifications	Until device unregistered or account deletion
Usage analytics	Auto	Product improvement, bug detection (anonymized)	24 months rolling window
Payment information	Premium	Subscription billing (handled by Stripe, not stored by PoshPet)	Managed by Stripe

6.3.2 Data Usage

Core functionality: All collected data used to provide app features as described

Analytics: Anonymized, aggregated usage data for product improvement

Notifications: Email and push for task reminders, kit steps, capsule delivery, account alerts

Never sold: PoshPet will NEVER sell, rent, or share personal data with third parties for advertising or marketing

Never shared: Personal data is never shared with other users unless explicitly done by the user (Care Circle posts, contributions)

No advertising: PoshPet does not display ads and does not share data with ad networks

6.3.3 Data Retention

Active accounts: All data retained as long as account is active

Deleted accounts: All personal data permanently deleted within 30 days of account deletion request. Anonymized aggregate analytics may be retained.

Deleted pets: Pet data soft-deleted for 90 days (recovery period), then permanently deleted

Time Capsules: Encrypted media deleted 90 days after capsule is opened. Sealed capsules retained until delivery + 90 days.

Backups: Database backups containing deleted data purged within 30 days of the data retention period

6.4 GDPR Compliance (EU Users)

If PoshPet accepts users from the European Union, the following GDPR requirements apply:

6.4.1 Lawful Basis for Processing

Contract: Processing necessary to provide the service (core functionality)

Consent: Explicit consent for marketing emails, push notifications, analytics cookies

Legitimate interest: Security, fraud prevention, service improvement

6.4.2 User Rights Implementation

Right	Implementation	Response Time
Right of Access	Settings > Privacy > 'Download My Data' button. Generates JSON/ZIP with all personal data.	Within 30 days
Right to Rectification	Users can edit all personal data directly in app (name, email, pet info). Support request for non-editable fields.	Immediate (self-service) or 30 days
Right to Erasure	Settings > Account > 'Delete My Account'. Confirmation required (type 'DELETE'). 14-day grace period for undo.	Completed within 30 days
Right to Portability	Same as Access. Data provided in machine-readable JSON format.	Within 30 days
Right to Restrict Processing	Support request. Account frozen (data retained but not processed).	Within 72 hours
Right to Object	Opt-out of analytics and marketing via Settings > Privacy.	Immediate

6.4.3 Data Processing Records

Maintain a Record of Processing Activities (ROPA) documenting: all data types collected, purposes, legal basis, storage locations, retention periods, third-party processors (Stripe, AWS/Cloudflare, Sentry, analytics provider), and security measures.

6.4.4 Data Protection Officer

Not required for a small business under 250 employees unless core activity involves large-scale processing of special categories. PoshPet does not process special category data. However, designate a contact email (privacy@poshpets.app) for data protection inquiries.

6.5 CCPA Compliance (California Users)

The California Consumer Privacy Act applies to businesses serving California residents.

6.5.1 Required Disclosures

'Do Not Sell My Personal Information' link: Must be visible in Settings > Privacy. PoshPet does not sell data, but the link must exist.

Categories of data collected: Must be disclosed (covered in Privacy Policy section 6.3.1)

Purpose of collection: Must be disclosed (covered in Privacy Policy section 6.3.2)

6.5.2 Consumer Rights

Right to Know: Same as GDPR Right of Access. 'Download My Data' button.

Right to Delete: Same as GDPR Right to Erasure. 'Delete My Account' button.

Right to Opt-Out: Opt-out of any data sharing (though PoshPet doesn't share data)

Non-Discrimination: Free tier users who exercise privacy rights receive identical service

6.6 App Store Requirements

6.6.1 Apple App Store (iOS)

Apple Sign-In: REQUIRED if any third-party sign-in (Google) is offered. Must be presented as equal option alongside Google Sign-In.

In-App Purchases: All subscriptions must go through Apple IAP. Cannot direct users to web for payment. 15% commission (30% if earning \$1M+/year).

Privacy Nutrition Labels: Must accurately declare all data types collected, linked to identity, and tracking practices in App Store Connect.

App Review Guidelines: No misleading health claims. Disclaimer about non-medical nature. Age rating: 4+ (no user-generated content visible to minors without moderation).

Data deletion: Must offer in-app account deletion. Apple requires this since 2022.

6.6.2 Google Play Store (Android)

Data Safety Section: Similar to Apple's nutrition labels. Declare all data collected, shared, and security practices.

Billing: Google Play Billing Library required for subscriptions. 15% commission (30% over \$1M).

Family Policy: If targeting families, additional requirements. PoshPet's audience is adults (28-45), so standard policies apply.

Data deletion: Must offer in-app account deletion. Google requires this since 2023.

6.7 Content Moderation Policies

Care Circles and photo galleries allow user-generated content. Moderation is required.

6.7.1 Prohibited Content

Sexual/NSFW content: Immediate removal, account suspension on first offense

Violence/abuse: Immediate removal, account suspension, report to authorities if animal abuse suspected

Harassment: Warning on first offense, suspension on second, permanent ban on third

Spam/advertising: Content removed, warning issued

Illegal content: Immediate removal, account suspension, authorities notified if required

Misinformation: Health misinformation in Care Circles removed with informational note

6.7.2 Moderation Methods

Automated: NSFW image detection (AWS Rekognition or similar) on all photo uploads. Flagged images held for manual review. Keyword filtering in Care Circle text posts.

User reporting: Report button on all user-generated content. Reports reviewed within 24 hours business days.

Admin review: Flagged content appears in admin panel moderation queue. Actions: approve, remove, warn user, suspend user.

Appeals: Users can appeal moderation decisions via support email. Response within 72 hours.

6.8 Data Security Standards

Minimum security requirements for PoshPet infrastructure:

6.8.1 Transport Security

TLS 1.3: All API communication over HTTPS with TLS 1.3 minimum

Certificate: Valid SSL certificate (auto-managed by hosting provider)

HSTS: HTTP Strict Transport Security header enabled

No mixed content: All resources (images, scripts, API calls) over HTTPS

6.8.2 Authentication Security

Password hashing: Bcrypt with minimum 12 rounds

JWT tokens: Access tokens: 15-minute expiry. Refresh tokens: 7-day expiry, single use, rotated on refresh.

Rate limiting: Login attempts: 5 failures per 15 minutes per IP, then 30-minute lockout. API requests: 100/minute per user.

2FA: Required for admin panel. Optional for users (Phase 2 consideration).

6.8.3 Data Encryption

At rest: Database encryption enabled (managed by hosting provider). Time Capsule media: AES-256-GCM with separate key per capsule.

In transit: TLS 1.3 for all network communication

Backups: Encrypted at rest using provider-managed keys

Secrets management: API keys, database credentials, encryption keys stored in environment variables. Never in source code. Rotated quarterly.

6.8.4 Infrastructure Security

Dependency scanning: Automated vulnerability scanning on npm packages (npm audit, Snyk, or Dependabot)

Access control: Principle of least privilege for all service accounts. Database accessible only from API server, not public internet.

Logging: All authentication events, data access, and admin actions logged. Logs retained 90 days.

Incident response: Document a basic incident response plan: detect, contain, eradicate, recover, review.

PART 7: TECHNICAL ARCHITECTURE

This section provides the consolidated technical foundation: system architecture, complete database table list, API conventions, scheduled jobs, file storage structure, and deployment specifications.

7.1 System Architecture Overview

PoshPet uses a standard three-tier architecture optimized for a solo founder with a growth path:

Tier 1: Client Layer

Mobile App: React Native 0.73+ (iOS + Android from single codebase)

Web App: React 18+ with Vite (responsive, mobile-first)

Admin Panel: React web app (separate route or subdomain)

All clients communicate with the API server via RESTful HTTPS endpoints. No direct database access from clients.

Tier 2: API Server

Runtime: Node.js 20 LTS

Framework: Express 4.x with TypeScript

ORM: Prisma 5.x

Responsibilities: Authentication, authorization, business logic, data validation, file processing, notification dispatch, cron job execution

Single server instance at launch. Horizontal scaling when needed (stateless design allows multiple instances behind load balancer).

Tier 3: Data Layer

Primary database: PostgreSQL 15+ (Supabase or Railway managed)

Cache: Redis (Upstash serverless or Railway)

File storage: Cloudflare R2 or AWS S3

CDN: Cloudflare (for static assets and Lottie animation files)

External Services

Authentication: Supabase Auth (or Firebase Auth / Auth0)

Payments: Stripe (subscriptions, webhooks)

Push notifications: Firebase Cloud Messaging (FCM for both iOS and Android)

Email: Mailgun, Resend, or SendGrid (transactional emails)

Error tracking: Sentry

Analytics: Mixpanel or Amplitude

Image moderation: AWS Rekognition (optional, can add post-launch)

7.2 Complete Database Table List

All 30+ tables organized by feature domain. Each table is fully defined in its respective feature document (Documents 2-4). This is the consolidated reference.

Core Tables

Table Name	Document	Purpose
users	N/A (standard)	User accounts, auth, profile data
pets	Doc 3 (5.12)	Pet profiles (name, species, breed, birthday, photo)
subscriptions	N/A (Stripe)	Subscription status, plan, Stripe IDs

Planner & Tasks

Table Name	Document	Purpose
task_templates	Doc 3 (5.10)	Recurring task definitions per pet
task_instances	Doc 3 (5.10)	Daily task instances with completion status
custom_trackers	Doc 2 (5.4)	User-created custom tracking items
planner_preferences	Doc 3 (5.13)	User planner settings (theme, visibility, style)

Progress & Achievements

Table Name	Document	Purpose
garden_state	Doc 2 (5.1)	Daily garden completion state per pet
garden_decor_unlocks	Doc 2 (5.1)	Unlocked decorative elements
garden_preferences	Doc 2 (5.1)	Active decor selections
task_streaks	Doc 2 (5.2)	Current and longest streaks per task
streak_milestones	Doc 2 (5.2)	Achieved badge milestones

Health Tracking

Table Name	Document	Purpose
weight_logs	Doc 2 (5.3)	Pet weight entries with date and unit
vet_visits	Doc 2 (5.3)	Veterinary visit records
vet_visit_attachments	Doc 2 (5.3)	Files attached to vet visits
medications	Doc 2 (5.3)	Medication definitions and schedules
medication_administrations	Doc 2 (5.3)	Individual dose administration logs

Media & Timeline

Table Name	Document	Purpose
photos	Doc 2 (5.5)	Pet photos with 3 size URLs and metadata
timeline_events	Doc 2 (5.7)	Auto-generated and manual timeline entries
pet_memorial	Doc 2 (5.7)	Memorial Mode activation records
pet_mood_state	Doc 2 (5.6)	Current avatar mood per pet

Social (Care Circles)

Table Name	Document	Purpose
care_circles	Doc 3 (5.8)	Circle definitions and settings
circle_members	Doc 3 (5.8)	Circle membership and roles
circle_posts	Doc 3 (5.8)	Shared content in circles
circle_comments	Doc 3 (5.8)	Comments on circle posts
circle_reactions	Doc 3 (5.8)	Reactions on circle posts
circle_reports	Doc 3 (5.8)	Reported content/users

Party Kits

Table Name	Document	Purpose
party_kit_templates	Doc 4 (5.14)	Kit template definitions (admin-managed)
party_kit_steps	Doc 4 (5.14)	Step templates within each kit
user_kit_progress	Doc 4 (5.14)	User's progress through a kit
user_kit_step_responses	Doc 4 (5.14)	Individual step responses (JSONB)
time_capsules	Doc 4 (5.14)	Sealed/delivered Time Capsules
memory_pages	Doc 4 (5.14)	Generated Memory Page content
circle_contributions	Doc 4 (5.14)	Care Circle contributions to kits

Notifications

Table Name	Document	Purpose
notification_preferences	Doc 3 (5.11)	User notification settings
notification_logs	Doc 3 (5.11)	Sent notification history and engagement

Total: 35 tables across 8 domains.

7.3 Cron Jobs (Scheduled Tasks)

The following background jobs run on schedules. Use node-cron or Bull queue for job scheduling.

Job Name	Schedule	Description	Priority
time_capsule_delivery	Daily 9:00 AM UTC	Check for capsules where delivery_date <= today AND status = 'sealed'. Trigger delivery notification for each matching capsule.	Critical
streak_reset_check	Daily 12:05 AM (per timezone)	For each user: check yesterday's task instances. If any task not completed and has active streak, reset streak to 0. Must run per-timezone for accuracy.	Critical
garden_state_reset	Daily 12:01 AM (per timezone)	Create new garden_state records for today. Set total_tasks based on active task templates. Set completed_tasks to 0.	High
task_instance_generation	Daily 12:02 AM (per timezone)	Generate today's task_instances from active task_templates. Check frequency rules (daily, weekly, etc.) and create instances accordingly.	High
notification_digest	Every 30 minutes	Process notification queue. Check quiet hours per user. Bundle notifications if 3+ pending within 30 minutes. Enforce daily limits.	Normal
kit_pacing_check	Daily 10:00 AM UTC	For active kits: check if next step should be prompted based on pacing algorithm. Send notification if appropriate.	Normal
expired_invite_cleanup	Daily 3:00 AM UTC	Delete expired Care Circle invite links (7+ days old) and expired QR codes (24+ hours old).	Low
photo_cleanup	Weekly Sunday 4:00 AM UTC	Remove orphaned photo files from storage (uploaded but never saved to database). Check for failed processing jobs and retry.	Low
analytics_snapshot	Daily 1:00 AM UTC	Capture daily metrics: DAU, task completions, Full Blooms, kit starts, capsules sealed. Store in analytics table for admin dashboard.	Low
backup_verification	Weekly Monday 5:00 AM UTC	Verify most recent database backup completed successfully. Alert admin if backup older than 48 hours.	Critical

7.4 API Conventions

All API endpoints follow consistent conventions for predictability and developer experience.

7.4.1 RESTful Design

Base URL: `https://api.poshpet.app/v1`

Versioning: URL path versioning (`/v1/`). Major version changes only for breaking changes.

Resources: Plural nouns (e.g., `/pets`, `/photos`, `/circles`). Nested resources for clear ownership (e.g., `/pets/{id}/photos`).

Methods: GET (read), POST (create), PUT (update), DELETE (remove). PATCH not used in Phase 1 for simplicity.

7.4.2 Authentication

Scheme: Bearer token in Authorization header

Authorization: Bearer <jwt_access_token>

Token refresh: POST `/auth/refresh` with refresh token in HTTP-only cookie or request body

Admin routes: Additional role check. Admin JWT contains role: 'superadmin' claim.

7.4.3 Request/Response Format

Content type: `application/json` for all requests and responses

File uploads: `multipart/form-data` for photo and media uploads only

Success Response:

```
{
  "success": true,
  "data": { ... },
  "meta": {
    "page": 1,
    "limit": 50,
    "total": 237,
    "has_more": true
  }
}
```

Error Response:

```
{
  "success": false,
  "error": {
    "code": "VALIDATION_ERROR",
    "message": "Pet name is required.",
    "field": "name"
  }
}
```

7.4.4 Error Codes

HTTP Status	Error Code	Description
400	VALIDATION_ERROR	Request body failed validation (missing/invalid fields)
401	UNAUTHORIZED	Missing or expired JWT token
403	FORBIDDEN	Valid token but insufficient permissions (e.g., free user accessing Premium feature)
403	SUBSCRIPTION_REQUIRED	Feature requires Premium subscription
404	NOT_FOUND	Requested resource does not exist or does not belong to user
409	CONFLICT	Resource already exists (e.g., duplicate circle membership)
413	FILE_TOO_LARGE	Uploaded file exceeds size limit
429	RATE_LIMITED	Too many requests. Retry after X seconds.
500	INTERNAL_ERROR	Unexpected server error (logged to Sentry)

7.4.5 Pagination

Style: Offset-based pagination for simplicity in Phase 1

Parameters: ?page=1&limit=50 (default limit: 50, max limit: 100)

Response: meta.page, meta.limit, meta.total, meta.has_more included in all paginated responses

Sort: Default: newest first (created_at DESC). Configurable: ?sort=created_at&order=asc

7.4.6 Rate Limiting

General: 100 requests per minute per authenticated user

Auth endpoints: 5 requests per 15 minutes per IP (login, register, password reset)

Upload endpoints: 10 requests per minute per user

Headers returned: X-RateLimit-Limit, X-RateLimit-Remaining, X-RateLimit-Reset

7.5 File Storage Structure

All user-uploaded files stored in Cloudflare R2 (or AWS S3) with the following bucket structure:

7.5.1 Bucket Layout

```
poshpets-media/
  photos/
    {user_id}/
      {pet_id}/
        {photo_id}_original.jpg
        {photo_id}_medium.jpg
        {photo_id}_thumbnail.jpg
  avatars/
    {user_id}/
      {pet_id}_avatar.jpg
  vet-attachments/
    {user_id}/
      {visit_id}/
        {attachment_id}.jpg
  circle-media/
    {circle_id}/
      {post_id}/
        {media_id}.jpg
  memory-pages/
    {user_id}/
      {page_id}_share.jpg
      {page_id}_export.pdf
  streak-badges/
    {user_id}/
      {milestone_id}_share.jpg

poshpets-capsules/      (SEPARATE BUCKET - restricted access)
  {user_id}/
    {capsule_id}.enc    (AES-256 encrypted media)

poshpets-static/        (PUBLIC CDN bucket)
  animations/
    avatars/            (16 Lottie files)
    garden/             (7 Lottie files)
    kits/               (11 Lottie files)
  icons/
  default-avatars/      (10 static species illustrations)
```

7.5.2 Access Policies

poshpets-media: Private. Signed URLs with 1-hour expiry generated on-demand by API.

poshpets-capsules: Private. Highly restricted. Signed URLs generated ONLY after delivery date verification. Separate IAM credentials from main bucket.

poshpets-static: Public read. Served via Cloudflare CDN with aggressive caching (30-day max-age).

7.6 Environment Variables

All secrets and configuration managed via environment variables. Never committed to source code.

Variable	Description	Example
DATABASE_URL	PostgreSQL connection string	postgresql://user:password@host:5432/poshpet
REDIS_URL	Redis connection string	redis://default:password@host:6379
JWT_SECRET	Secret key for JWT signing (256-bit minimum)	random-256-bit-string
JWT_REFRESH_SECRET	Separate secret for refresh tokens	random-256-bit-string
STRIPE_SECRET_KEY	Stripe API secret key	sk_live_...
STRIPE_WEBHOOK_SECRET	Stripe webhook signing secret	whsec_...
STRIPE_PRICE_MONTHLY	Stripe Price ID for monthly plan	price_...
STRIPE_PRICE_ANNUAL	Stripe Price ID for annual plan	price_...
R2_ACCOUNT_ID	Cloudflare R2 account ID	abc123...
R2_ACCESS_KEY	R2 access key	...
R2_SECRET_KEY	R2 secret key	...
R2_BUCKET_MEDIA	Media bucket name	poshpet-media
R2_BUCKET_CAPSULES	Capsules bucket name (restricted)	poshpet-capsules
R2_BUCKET_STATIC	Static assets bucket name	poshpet-static
FCM_SERVER_KEY	Firebase Cloud Messaging key	...
SENTRY_DSN	Sentry error tracking DSN	https://...@sentry.io/...
ADMIN_EMAIL	Superadmin email address	admin@poshpet.app
APP_URL	Frontend app URL	https://app.poshpet.app
API_URL	API server URL	https://api.poshpet.app
NODE_ENV	Environment (development/staging/production)	production
CAPSULE_ENCRYPTION_MASTER_KEY	Master key for Time Capsule encryption key derivation	random-256-bit-string

7.7 Error Handling Standards

Consistent error handling across the entire API:

7.7.1 Validation Errors

All request bodies validated using Zod schemas before processing. Validation errors return 400 with field-specific messages. Schema definitions shared between frontend and backend for consistency.

7.7.2 Business Logic Errors

Free tier limits: Return 403 SUBSCRIPTION_REQUIRED with clear message: 'Upgrade to PoshPet Society to add more pets.'

Resource ownership: All queries scoped to authenticated user_id. Return 404 (not 403) if resource belongs to another user (prevents enumeration).

Concurrent modifications: Optimistic locking with updated_at timestamp checks where needed (kit step responses, contribution edits).

7.7.3 Error Logging

All 5xx errors: Automatically reported to Sentry with full stack trace, request context, and user ID (anonymized)

All 4xx errors: Logged locally with request details. NOT reported to Sentry (too noisy).

Critical failures: Database connection failures, Stripe webhook failures, capsule encryption errors trigger Sentry alert + email to admin.

7.8 Deployment Checklist

Pre-launch checklist for the developer:

7.8.1 Infrastructure Setup

- ☐ PostgreSQL database provisioned and accessible
- ☐ Redis instance provisioned and accessible
- ☐ Cloudflare R2 buckets created (media, capsules, static)
- ☐ API server deployed and responding to health check
- ☐ Web frontend deployed and loading
- ☐ DNS configured (app.poshpet.app, api.poshpet.app, admin.poshpet.app)
- ☐ SSL certificates active on all domains
- ☐ CDN configured for static assets

7.8.2 Services Configuration

- ☐ Stripe account configured with products and prices
- ☐ Stripe webhooks registered and verified
- ☐ Firebase project created, FCM enabled
- ☐ Sentry project created, DSN configured
- ☐ Email service configured (transactional emails tested)
- ☐ Analytics SDK integrated and sending events

7.8.3 Database & Data

- ☐ All Prisma migrations applied successfully
- ☐ Seed data loaded: 4 Party Kit templates with all steps
- ☐ Seed data loaded: default task templates for all 14 species
- ☐ Admin user account created
- ☐ Database backups configured and verified

7.8.4 Media & Assets

- ☐ All 16 avatar Lottie animations uploaded to static bucket
- ☐ All 7 garden Lottie animations uploaded
- ☐ All 11 Party Kit Lottie animations uploaded
- ☐ 10 static species illustrations uploaded
- ☐ Default badge images uploaded
- ☐ CDN cache headers configured (30-day max-age for animations)

7.8.5 Security Verification

- ☐ All environment variables set (none missing, none hardcoded)
- ☐ JWT secrets are unique, random, 256-bit minimum

- ☐ Database not accessible from public internet
- ☐ R2 capsule bucket has restricted access policy
- ☐ Rate limiting active on all endpoints
- ☐ CORS configured (allow only app.poshpet.app origins)
- ☐ HSTS header enabled
- ☐ npm audit shows no critical vulnerabilities

7.8.6 App Store Submission

- ☐ Apple Developer Account active (\$99/year)
- ☐ Google Play Developer Account active (\$25 one-time)
- ☐ App Store screenshots prepared (6.7", 6.5", 5.5", iPad)
- ☐ Play Store screenshots prepared
- ☐ App description, keywords, and category selected
- ☐ Privacy Policy URL live and accessible
- ☐ Terms of Service URL live and accessible
- ☐ Privacy Nutrition Labels completed (Apple)
- ☐ Data Safety form completed (Google)
- ☐ Apple Sign-In implemented and tested
- ☐ In-App Purchase products created and submitted for review
- ☐ Test account credentials prepared for App Store reviewer

7.8.7 Testing

- ☐ Full user flow tested: signup → add pet → complete tasks → Full Bloom
- ☐ Subscription flow tested: free → trial → paid → cancel → downgrade
- ☐ Party Kit flow tested: start → all steps → completion → Memory Page
- ☐ Time Capsule tested: record → seal → delivery (use test date override)
- ☐ Care Circle tested: create → invite → join → post → contribute to kit
- ☐ Memorial Mode tested: activation → visual changes → capsule release → PDF export
- ☐ Notification delivery tested (push, in-app)
- ☐ Offline handling tested (graceful degradation, sync on reconnect)
- ☐ Accessibility tested (VoiceOver/TalkBack, reduced motion)
- ☐ Performance tested (app load under 2 seconds, 60fps animations)

END OF DOCUMENT 5: LEGAL & TECHNICAL ARCHITECTURE

This document covers all non-feature technical requirements:

- 6.1 — Medical disclaimers with exact text and placement rules
- 6.2 — Terms of Service summary including subscription terms
- 6.3 — Privacy Policy with data collected table and retention rules
- 6.4 — GDPR compliance with user rights implementation table
- 6.5 — CCPA compliance requirements
- 6.6 — Apple App Store and Google Play Store requirements
- 6.7 — Content moderation policies and methods
- 6.8 — Data security standards (TLS, auth, encryption, infrastructure)
- 7.1 — Three-tier system architecture overview
- 7.2 — Complete database table list (35 tables across 8 domains)
- 7.3 — 10 cron jobs with schedules and priorities
- 7.4 — API conventions (REST, auth, pagination, rate limits, error codes)
- 7.5 — File storage structure (3 buckets, directory layout, access policies)
- 7.6 — 21 environment variables
- 7.7 — Error handling standards
- 7.8 — Deployment checklist (7 sections, 40+ verification items)

COMPLETE DOCUMENTATION SET

The full PoshPet Phase 1 Technical Documentation consists of 5 documents:

Document 1: Foundation — Project overview, tech stack, design system, roadmap (~15 pages)

Document 2: Core Features — Garden, streaks, health, trackers, photos, avatar, timeline (~45 pages)

Document 3: Social, Planner & System — Circles, planner, notifications, pet selector, admin, AI, exclusions (~25 pages)

Document 4: Party Kits — Complete Party Kit specification with all 4 kits (~40 pages)

Document 5: Legal & Architecture — Compliance, security, database, API, deployment (~16 pages)

TOTAL: Approximately 120 pages of complete developer-ready specifications.

PoshPet: Turn daily pet care into a love story — captured forever, celebrated intentionally, remembered always.